

---

# **Earth Diagnostics Documentation**

***Release 3.0.0b37***

**BSC-CNS Earth Sciences Department**

Jan 27, 2017



<b>1</b>	<b>Tutorial</b>	<b>1</b>
1.1	Installation . . . . .	1
1.2	Creating a config file . . . . .	1
1.3	Prepare the run script . . . . .	2
<b>2</b>	<b>Configuration file options</b>	<b>3</b>
2.1	DIAGNOSTICS . . . . .	3
2.1.1	Mandatory configurations . . . . .	3
2.1.2	Optional configurations . . . . .	3
2.2	EXPERIMENT . . . . .	4
2.3	CMOR . . . . .	4
2.3.1	Cmorization options . . . . .	4
2.3.2	Metadata options . . . . .	5
2.4	THREDDS . . . . .	5
2.5	ALIAS . . . . .	6
<b>3</b>	<b>Diagnostic list</b>	<b>7</b>
3.1	General . . . . .	7
3.1.1	att . . . . .	7
3.1.2	monmean . . . . .	7
3.1.3	relink . . . . .	8
3.1.4	relinkall . . . . .	8
3.1.5	rewrite: . . . . .	8
3.1.6	scale . . . . .	8
3.2	Ocean . . . . .	9
3.2.1	areamoc . . . . .	9
3.2.2	averagesection . . . . .	9
3.2.3	convectionsites . . . . .	10
3.2.4	cutsection . . . . .	10
3.2.5	gyres . . . . .	10
3.2.6	heatcontent . . . . .	10
3.2.7	heatcontentlayer . . . . .	11
3.2.8	interpolate . . . . .	11
3.2.9	interpolateCDO . . . . .	11
3.2.10	maxmoc . . . . .	12
3.2.11	mixedlayerheatcontent . . . . .	12
3.2.12	mixedlayersaltcontent . . . . .	12
3.2.13	moc . . . . .	12
3.2.14	psi . . . . .	13
3.2.15	regmean . . . . .	13
3.2.16	siasiesiv . . . . .	13

3.2.17	verticalmean	13
3.2.18	verticalmeanmeters	14
3.3	Statistics	14
3.3.1	climpercent	14
3.3.2	monpercent	14
<b>4</b>	<b>Tips and tricks</b>	<b>15</b>
4.1	Working with ORCA1	15
4.2	Configuring core usage	15
4.3	NEMO files	15
<b>5</b>	<b>What to do if you have an error</b>	<b>17</b>
<b>6</b>	<b>Developer's guide</b>	<b>19</b>
6.1	Developing a diagnostic	19
<b>7</b>	<b>Frequently Asked Questions</b>	<b>21</b>
<b>8</b>	<b>Module documentation</b>	<b>23</b>
8.1	earthdiagnostics	23
8.1.1	earthdiagnostics.box	23
8.1.2	earthdiagnostics.cdftools	24
8.1.3	earthdiagnostics.cmorizer	24
8.1.4	earthdiagnostics.cmormanager	24
8.1.5	earthdiagnostics.config	27
8.1.6	earthdiagnostics.constants	28
8.1.7	earthdiagnostics.datamanager	32
8.1.8	earthdiagnostics.diagnostic	35
8.1.9	earthdiagnostics.earthdiags	36
8.1.10	earthdiagnostics.parser	37
8.1.11	earthdiagnostics.utils	40
8.1.12	earthdiagnostics.variable	43
8.2	earthdiagnostics.general	44
8.2.1	earthdiagnostics.general.attribute	44
8.2.2	earthdiagnostics.general.monthlymean	44
8.2.3	earthdiagnostics.general.relink	45
8.2.4	earthdiagnostics.general.relinkall	46
8.2.5	earthdiagnostics.general.rewrite	46
8.2.6	earthdiagnostics.general.scale	47
8.3	earthdiagnostics.ocean	48
8.3.1	earthdiagnostics.ocean.areamoc	48
8.3.2	earthdiagnostics.ocean.averagesection	49
8.3.3	earthdiagnostics.ocean.convectionsites	49
8.3.4	earthdiagnostics.ocean.cutsection	50
8.3.5	earthdiagnostics.ocean.gyres	51
8.3.6	earthdiagnostics.ocean.heatcontent	52
8.3.7	earthdiagnostics.ocean.heatcontentlayer	52
8.3.8	earthdiagnostics.ocean.interpolate	53
8.3.9	earthdiagnostics.ocean.interpolatecd	54
8.3.10	earthdiagnostics.ocean.maxmoc	55
8.3.11	earthdiagnostics.ocean.mixedlayerheatcontent	55
8.3.12	earthdiagnostics.ocean.mixedlayersaltcontent	56
8.3.13	earthdiagnostics.ocean.moc	57
8.3.14	earthdiagnostics.ocean.psi	57
8.3.15	earthdiagnostics.ocean.siasiesiv	58

8.3.16	earthdiagnostics.ocean.verticalmean . . . . .	59
8.3.17	earthdiagnostics.ocean.verticalmeanmeters . . . . .	59
8.4	earthdiagnostics.statistics . . . . .	60
8.4.1	earthdiagnostics.statistics.climatologicalpercentile . . . . .	60
8.4.2	earthdiagnostics.statistics.monthlypercentile . . . . .	61
<b>Python Module Index</b>		<b>63</b>
<b>Index</b>		<b>65</b>



## TUTORIAL

So, you are planning to use the Earth Diagnostics? You don't know how to use them? This is the place to go. From now on this tutorial will guide you through all the process from installation to running.

---

**Hint:** If you have any problem with this tutorial, please report it to <[javier.vegas@bsc.es](mailto:javier.vegas@bsc.es)> so it can be corrected. A lot of people will benefit from it.

---

### 1.1 Installation

If you have access to the BSC-ES machines, you don't need to install it. Just use the available module:

In case that you need a custom installation for development or can not use the BSC-ES machines, install it from BSC-ES GitLab repository:

```
pip install git+https://earth.bsc.es/gitlab/es/ocean_diagnostics.git
```

You will also need

- CDO version 1.7.2 (other versions could work, but this is the one we use)
- NCO version 4.5.4 or newer
- Python 2.7 or newer (but no 3.x) with bscearth.utils, CDO and NCO packages, among others.
- Access to CDFTOOLS\_3.0 executables for BSC-ES. The source code is available on Github (<https://github.com/jvegasbsc/CDFTOOLS>) and it can be compiled with CMake

### 1.2 Creating a config file

Go to the folder where you installed the EarthDiagnostics. You will see a folder called earthdiagnostics, and, inside it, a diags.conf file that can be used as a model for your config file. Create a copy of it wherever it suits you.

Now open your brand new copy with your preferred text editor. The file contains commentaries explaining each one of its options, so read it carefully and edit whatever you need. Don't worry about DIAGS option, we will talk about it next.

After this, you need to choose the diagnostics you want to run. For a simple test, it's recommended to use the monmean diagnostic to compute monthly means from daily data. We recommend it because it can be used with any variable, the user has to provide parameters but they are quite intuitive and it's relatively fast to compute. If your experiment does not have daily data, you can use any other diagnostic. Check next section for a list of available diagnostics and choose whichever suits you better. From now on, we will assume that you are going to run the monmean diagnostic.

---

**Hint:** For old Ocean Diagnostics users: you can use most of the old names as aliases to launch one or multiple diagnostics. Check the ALIAS section on the diags.conf to see which ones are available.

---

First, choose a variable that has daily data. Then replace the DIAGS option with the next one where \$VARIABLE represents the variable's name and \$DOMAIN its domain (atmos, ocean, seaice, landice...)

```
DIAGS = monmean, $VARIABLE, $DOMAIN
```

## 1.3 Prepare the run script

Once you have configured your experiment you can execute any diagnostic with the provided launch\_diags.sh script. Create a copy and change the variables PATH\_TO\_CONF\_FILE and PATH\_TO\_DIAGNOSTICS so they point to your conf file and installation folder.

Now, execute the script (or submit it to bsclogin01, it has the correct header) and... that's it! You will find your results directly on the storage and a folder for the temp files in the scratch named after the EXPID.

## CONFIGURATION FILE OPTIONS

This section contains the list and explanation about all the options that are available on the configuration file. Use it as a reference while preparing your configuration file. Each subsection will refer to the matching section from the config file. Those subsections explanation may be divided itself for the shake of clarity but this further divisions have nothing to do with the config file syntax itself.

### 2.1 DIAGNOSTICS

This section contains the general configuration for the diagnostics. The explanation has been divided in two subsections: the first one will cover all the mandatory options that you must specify in every configuration, while the second will cover all the optional configurations.

#### 2.1.1 Mandatory configurations

- **SCRATCH\_DIR:** Temporary folder for the calculations. Final results will never be stored here.
- **DATA\_DIR:** ‘.’ separated list of folders to look for data in. It will look for file in the path \$DATA\_FOLDER/\$EXPID and \$DATA\_FOLDER/\$DATA\_TYPE/\$MODEL/\$EXPID
- **CON\_FILES:** Folder containing mask and mesh files for the dataset.
- **FREQUENCY:** Default data frequency to be used by the diagnostics. Some diagnostics can override this configuration or even ignore it completely.

#### 2.1.2 Optional configurations

- **DATA\_ADAPTOR** This is used to choose the mechanism for storing and retrieving data. Options are CMOR (for our own experiments) or THREDDS (for anything else). Default value is CMOR
- **DATA\_TYPE** Type of the dataset to use. It can be exp, obs or recon. Default is exp.
- **DATA\_CONVENTION** Convention to use for file paths and names and variable naming among other things. Can be SPECS, PRIMAVERA or CMIP6. Default is SPECS.
- **CDFTOOLS\_PATH** Path to the folder containing CDFTOOLS executables. By default is empty, so CDFTOOLS binaries must be added to the system path.
- **MAX\_CORES** Maximum number of cores to use. By default the diagnostics will use all cores available to them. It is not necessary when launching through a scheduler, as Earthdiagnostics can detect how many cores the scheduler has allocated to it.

## 2.2 EXPERIMENT

This sections contains options related to the experiment's definition or configuration.

- **MODEL** Name of the model used for the experiment.
- **MODEL\_VERSION** Model version. Used to get the correct mask and mesh files
- **ATMOS\_TIMESTEP** Time between outputs from the atmosphere. This is not the model simulation timestep!
- **OCEAN\_TIMESTEP** Time between outputs from the ocean. This is not the model simulation timestep!
- **ATMOS\_GRID** Atmospheric grid definition. Will be used as a default target for interpolation diagnostics.
- **INSTITUTE** Institute that made the experiment, observation or reconstruction
- **EXPID** Unique identifier for the experiment
- **NAME** Experiment's name. By default it is the EXPID.
- **STARTDATES** Startdates to run as a space separated list
- **MEMBER** Members to run as a space separated integer list
- **MEMBER\_DIGITS** Number of minimum digits to compose the member name. By default it is 1. For example, for member 1 member name will be fc1 if MEMBER\_DIGITS is 1 or fc01 if MEMBER\_DIGITS is 2
- **CHUNK\_SIZE** Length of the chunks in months
- **CHUNKS** Number of chunks to run
- **CALENDAR** Calendar to use for date calculation. All calendars supported by Autosubmit are available. Default is 'standard'

## 2.3 CMOR

In this section, you can control how will work the cmorization process. All options belonging to this section are optional.

### 2.3.1 Cmorization options

This options control when and which varibales will be cmorized.

- **FORCE** If True, launches the cmorization, regardless of existence of the extracted files or the package containing the online-cmorized ones. If False, only the non-present chunks will be cmorized. Default value is False
- **FORCE\_UNTAR** Unpacks the online-cmorized files regardless of exstience of extracted files. If 'FORCE is True, this parameter has no effect. If False, only the non-present chunks will be unpacked. Default value is False.
- **FILTER\_FILES** Only cmorize original files containing any of the given strings. This is a space separated list. Default is the empty string.
- **OCEAN\_FILES** Boolean flag to activate or no NEMO files cmorization. Default is True.
- **ATMOSPHERE\_FILES** Boolean flag to activate or no IFS files cmorization. Default is True.

- **USE\_GRIB** Boolean flag to activate or no GRIB files cmorization for the atmosphere. If activated and no GRIB files are present, it will cmorize using the MMA files instead (as if it was set to False). Default is True.
- **CHUNKS** Space separated list of chunks to be cmorized. If not provided, all chunks are cmorized
- **VARIABLE\_LIST** Space separated list of variables to cmorize. Variables must be specified as domain:var\_name. If no one is specified, all the variables will be cmorized

### Grib variables extraction

These three options are used to configure the variables to be CMORized from the grib atmospheric files. They must be specified using the IFS code in a list separated by comma.

You can also specify the levels to extract using one of the the following syntaxes:

- **VARIABLE\_CODE**
- **VARIABLE\_CODE:LEVEL**,
- **VARIABLE\_CODE:LEVEL\_1-LEVEL\_2-...-LEVEL\_N**
- **VARIABLE\_CODE:MIN\_LEVEL:MAX\_LEVEL:STEP**

Some examples to clarify it further: \* Variable with code 129 at level 30000: 129:30000 \* Variable with code 129 at levels 30000, 40000 and 60000: 129:30000-40000-60000 \* Variable with code 129 at levels between 30000 and 60000 with 10000 intervals:

129:30000:60000:10000 equivalent to 129:30000-40000-50000-60000

- **ATMOS\_HOURLY\_VARS** Configuration of variables to be extracted in an hourly basis
- **ATMOS\_DAILY\_VARS** Configuration of variables to be extracted in a daily basis
- **ATMOS\_MONTHLY\_VARS** Configuration of variables to be extracted in a monthly basis

### 2.3.2 Metadata options

All the options in this subsection will serve just to add the given values to the homonymous attributes in the cmorized files.

- **ASSOCIATED\_EXPERIMENT** Default value is 'to be filled'
- **ASSOCIATED\_MODEL** Default value is 'to be filled'
- **INITIALIZATION\_DESCRIPTION** Default value is 'to be filled'
- **INITIALIZATION\_METHOD** Default value is '1'
- **PHYSICS\_DESCRIPTION** Default value is 'to be filled'
- **PHYSICS\_VERSION** Default value is '1'
- **SOURCE** Default value is 'to be filled'

## 2.4 THREDDS

For now, there is only one option for the THREDDS server configuration.

- **SERVER\_URL** THREDDS server URL

## 2.5 ALIAS

This config file section is different from all the others because it does not contain a set of configurations. Instead, in this section the user can define a set of aliases to be able to launch its most used configurations with ease. To do this, the user must add an option with named after the desired alias and assign to it the configuration or configurations to launch when this ALIAS is invoked. See the next example:

```
ALIAS_NAME = diag,opt1,opt2 diag,opt1new,opt2
```

In this case, the user has defined a new alias 'ALIAS' that can be used launch two times the diagnostic 'diag', the first with the options 'opt1' and 'opt2' and the second replacing 'opt1' with 'opt1new'.

In this example, configuring the DIAGS as

```
DIAGS = ALIAS_NAME
```

will be identical to

```
DIAGS = diag,opt1,opt2 diag,opt1new,opt2
```

```
# coding=utf-8
```

## DIAGNOSTIC LIST

In this section you have a list of the available diagnostics, with a small description of each one and a link to the full documentation. To see what options are available for each diagnostic, see [generate\\_jobs](#) documentation.

Remember that diagnostics are specified separated by spaces while options are given separated by commas:

```
DIAGS = diag1 diag2,option1,option2 diag3
```

### 3.1 General

The diagnostics from this section are of general use and can be used with any variable you may have. Most of them are meant to help you to solve usual issues that you may have with the data: incorrect metadata, scaled up or down variables, links missing. This section also contains the diagnostic used to calculate the monthly means.

#### 3.1.1 att

Writes a global attributte to all the netCDF files for a given variable. See [Attribute](#)

##### Options:

1. **Variable:** Variable name
2. **Domain:** Variable domain
3. **Attributte name:** Attributte to write
4. **Attribute value:** Attribute's new value. Replace ',' with '&,' and ' ' with '&.' to avoid parsing errors when processing the diags
5. **Grid = "":** Variable grid. Only required in case that you want to use interpolated data.

#### 3.1.2 monmean

Calculates the monthly mean for a given variable. See [MonthlyMean](#)

**Warning:** This diagnostic does not use the frequency configuration from the config file. You must specify the original frequency when calling it. Otherwise, it will always try to use daily data.

**Options:**

1. **Variable:** Variable name
2. **Domain:** Variable domain
3. **Original frequency = daily:** Original frequency to use
4. **Grid = “:** Variable grid. Only required in case that you want to use interpolated data.

### 3.1.3 relink

Regenerates the links created in the monthly\_mean, daily\_mean, etc folders for a given variable. See [Relink](#)

**Options:**

1. **Variable:** Variable name
2. **Domain:** Variable domain
3. **Move old = True:** If True, any data founded in the target directory will be moved to another folder (called FOLDER\_NAME\_old) instead of deleted.
4. **Grid = “:** Variable grid. Only required in case that you want to use interpolated data.

### 3.1.4 relinkall

Regenerates the links created in the monthly\_mean, daily\_mean, etc folders for all variables See [RelinkAll](#)

**Options:**

This diagnostic has no options

### 3.1.5 rewrite:

Just rewrites the CMOR output of a given variable. Useful to correct metadata or variable units. See [Rewrite](#)

**Options:**

1. **Variable:** Variable name
2. **Domain:** Variable domain
3. **Grid = “:** Variable grid. Only required in case that you want to use interpolated data.

### 3.1.6 scale

Scales a given variable using a given scale factor and offset ( $NEW\_VALUE = OLD\_VALUE * scale + offset$ ). Useful to correct errors on the data.

See [Scale](#)

**Options:**

1. **Variable:** Variable name
2. **Domain:** Variable domain
3. **Scale value:** Scale factor for the variable
4. **Offset value:** Value to add to the original value after scaling
5. **Grid = “”:** Variable grid. Only required in case that you want to use interpolated data.
6. **Min limit = NaN:** Values below this will not be changed
7. **Max limit = NaN:** Values over this will not be changed

## 3.2 Ocean

The diagnostics from this section are meant to be used with NEMO variables. Some of them will compute new variables while others just calculate means or sections for variables in the ORCA grid. The interpolation diagnostics are also included here as they are usually used with variables in the ORCA grid.

### 3.2.1 areamoc

Compute an Atlantic MOC index by averaging the meridional overturning in a latitude band between 1km and 2km or any other index averaging the meridional overturning in a given basin and a given domain. See [AreaMoc](#)

**Warning:** The MOC for the given basin must be calculated previously. Usually, it will suffice to call the ‘moc’ diagnostic earlier in the DIAGS list.

**Options:**

1. **Min latitude:** Minimum latitude to compute
2. **Max latitude:** Maximum latitude to compute
3. **Min depth:** Minimum depth (in levels)
4. **Max depth:** Maximum depth (in levels)
5. **Basin = ‘Global’:** Basin to calculate the diagnostic on.

### 3.2.2 averagesection

Compute an average of a given zone. The variable **MUST** be in a regular grid See [AverageSection](#)

**Options:**

1. **Variable:** Variable to average
2. **Min longitude:** Minimum longitude to compute
3. **Max longitude:** Maximum longitude to compute
4. **Min latitude:** Minimum latitude to compute

5. **Max latitude:** Maximum latitude to compute
6. **Domain = ocean:** Variable domain

### 3.2.3 convectionsites

Compute the intensity of convection in the four main convection sites. See *ConvectionSites*

#### Options:

This diagnostic has no options

### 3.2.4 cutsection

Cuts a meridional or zonal section. See *CutSection*

#### Options:

1. **Variable:** Variable to cut the section on
2. **Zonal:** If True, calculates a zonal section. If False, it will be a meridional one
3. **Value:** Reference value for the section
4. **Domain = ocean:** Variable's domain

### 3.2.5 gyres

Compute the intensity of the subtropical and subpolar gyres. See *Gyres*

#### Options:

This diagnostic has no options

### 3.2.6 heatcontent

Compute the total and mean ocean heat content. See *HeatContent*

#### Options:

1. **Basin** Basin to calculate the heat content one
2. **Mixed layer:** If 1, reduces the computation to the mixed layer. If -1, excludes the mixed layer from the computations. If 0, no effect.
3. **Min depth:** Minimum depth for the calculation in levels. If 0, whole depth is used
4. **Max depth:** Maximum depth for the calculation in levels

### 3.2.7 heatcontentlayer

Point-wise Ocean Heat Content in a specified ocean thickness. See *HeatContentLayer*

#### Options:

3. **Min depth:** Minimum depth for the calculation in meters
4. **Max depth:** Maximum depth for the calculation in meters
5. **Basin = 'Global':** Basin to calculate the heat content on.

```
options_available = (DiagnosticIntOption('min_depth'), DiagnosticIntOption('max_depth'),
                    DiagnosticBasinOption('basin', Basins.Global))
```

### 3.2.8 interpolate

3-dimensional conservative interpolation to the regular atmospheric grid. It can also be used for 2D (i,j) variables. See *Interpolate*

**Warning:** This interpolation requires the pre-generated weights that can be found in '/es-nas/autosubmit/con\_files/weights'. Make sure that they are available for your configuration.

#### Options:

1. **Target grid:** New grid for the data
2. **Variable:** Variable to interpolate
3. **Domain = ocean:** Variable's domain
4. **Invert latitude:** If True, inverts the latitude in the output file.

### 3.2.9 interpolateCDO

Bilinear interpolation to a given grid using CDO. See *InterpolateCDO*

**Warning:** This interpolation is non-conservative, so treat its output with care. It has the advantage that does not require the pre-generated weights so it can be used when the 'interp' diagnostic is not available.

#### Options:

1. **Variable:** variable to interpolate
2. **Target grid:** Variable domain
3. **Domain = ocean:** Variable's domain
4. **Mask oceans = True:** If True, replaces the values in the ocean by NaN. You must only set it to false if, for some reason, you are interpolating an atmospheric or land variable that is stored in the NEMO grid (yes, this can happen, i.e. with tas).

### 3.2.10 maxmoc

Compute an Atlantic MOC index by finding the maximum of the annual mean meridional overturning in a latitude / depth region. Output from this diagnostic will be always in yearly frequency. See [MaxMoc](#)

**Warning:** The MOC for the given basin must be calculated previously. Usually, it will suffice to call the ‘moc’ diagnostic earlier in the DIAGS list.

**Warning:** This diagnostic can only be computed for full years. It will discard incomplete years and only compute the index in those with the full 12 months available.

#### Options:

1. **Min latitude:** Minimum latitude to compute
2. **Max latitude:** Maximum latitude to compute
3. **Min depth:** Minimum depth (in levels)
4. **Max depth:** Maximum depth (in levels)
5. **Basin = ‘Global’:** Basin to calculate the diagnostic on.

### 3.2.11 mixedlayerheatcontent

Compute mixed layer heat content. See [MixedLayerHeatContent](#)

#### Options:

This diagnostic has no options

### 3.2.12 mixedlayersaltcontent

Compute mixed layer salt content. See [MixedLayerSaltContent](#)

#### Options:

This diagnostic has no options

### 3.2.13 moc

Compute the MOC for oceanic basins. Required for ‘areamoc’ and ‘maxmoc’ See [Moc](#)

#### Options:

This diagnostic has no options

### 3.2.14 psi

Compute the barotropic stream function. See *Psi*

#### Options:

This diagnostic has no options

### 3.2.15 regmean

Compute an average of a given zone using cdfmean from CDFTOOLS See *RegionMean*

**Warning:** This diagnostic is a recent addition and needs more testing to be reliable

#### Options:

1. **Domain:** Variable domain
2. **Variable:** Variable to average
3. **Grid:** NEMO grid used to store the variable: T, U, V ...
4. **Basin = Global:** Basin to compute
5. **Save 3d = False:** If True, it also stores the average per level
6. **Min depth:** Minimum depth to compute in levels. If -1, average from the surface
7. **Max depth:** Maximum depth to compute in levels. If -1, average to the bottom

### 3.2.16 siasiesiv

Compute the sea ice extent , area and volume in both hemispheres or a specified region. See *Siasiesiv*

#### Options:

1. **Basin = 'Global':** Basin to restrict the computation to.

### 3.2.17 verticalmean

Chooses vertical level in ocean, or vertically averages between 2 or more ocean levels. See *VerticalMean*

#### Options:

1. **Variable:** Variable to average
2. **Min depth = -1:** Minimum level to compute. If -1, average from the surface
3. **Max depth:** Maximum level to compute. If -1, average to the bottom

### 3.2.18 verticalmeanmeters

Averages vertically any given variable. See *VerticalMeanMeters*

#### Options:

1. **Variable:** Variable to average
2. **Min depth = -1:** Minimum depth to compute in meters. If -1, average from the surface
3. **Max depth:** Maximum depth to compute in meters. If -1, average to the bottom

## 3.3 Statistics

### 3.3.1 climpercent

Calculates the specified climatological percentile of a given variable. See *ClimatologicalPercentile*

#### Options:

1. **Domain:** Variable's domain
2. **Variable:** Variable to compute diagnostic on
3. **Leadtimes:** Leadtimes to compute
4. **Bins:** Number of bins to use to discretize the variable

### 3.3.2 monpercent

Calculates the specified monthly percentile of a given variable. See *MonthlyPercentile*

#### Options:

1. **Domain:** Variable's domain
2. **Variable:** Variable to compute diagnostic on
3. **Percentiles:** List of requested percentiles ('-' separated)

## TIPS AND TRICKS

### 4.1 Working with ORCA1

If you plan to run diagnostics for ORCA1 resolution, be aware that your workstation will be more than capable to run them. At this resolution, memory and CPU consumption is low enough to allow you keep using the machine while running, specially if you reserve a pair of cores for other uses.

### 4.2 Configuring core usage

By default, the Earth Diagnostics creates a thread for each available core for the execution. If you are using a queueing system, the diagnostics will always use the number of cores that you reserved. If you are running outside a queueing system, the diagnostics will try to use all the cores on the machine. To avoid this, add the `MAX_CORES` parameter to the `DIAGNOSTICS` section inside the `diags.conf` file that you are using.

### 4.3 NEMO files

Unlike the bash version of the ocean diagnostics, this program keeps the NEMO files in the scratch folder so you can launch different configurations for the same experiment with reduced start time. You will need to remove the experiment's folder in the scratch directory at the end of the experiment to avoid wasting resources.



## WHAT TO DO IF YOU HAVE AN ERROR

Sometimes, the diagnostics may crash and you will not know why. This section will give you a procedure to follow before reporting the issue. This procedure is intended to solve some common problems or, at least, to help you in creating good issue reports. Remember: a good issue report reduces the time required to solve it!

---

**Hint:** Please, read carefully the error message. Most times the error message will point you to the problem's source and sometimes even give you a hint of how to solve it by yourself. And if this is not the case or if you find it obscure, even if it was helpful, please contact the developers so it can be improved in further versions

---

Try this simple steps BEFORE reporting an issue

- Clean scratch folder
- Update to the latest compatible tag: maybe your issue is already solved in it
- If you get the error for the first chunk of a given diagnostic, change the number of chunks to 1
- Call the diags with the `-lc DEBUG -log log.txt` options

Now, you have two options: if everything is fine, the error was probably due to some corrupted files or some unstable machine state. Nevertheless, try running the diagnostic with `-lc DEBUG -log log.txt` for all the chunks. If everything it's fine that's all.

If you experienced the same problem again, go to the GitLab portal and look into the open issues ( [https://earth.bsc.es/gitlab/es/ocean\\_diagnostics/issues](https://earth.bsc.es/gitlab/es/ocean_diagnostics/issues) ). If you find your issue or a very similar one, use it to report your problems. If you can not find an open one that suites your problem, create a new one and explain what is happening to you. In any case, it will be very useful if you can attach your `diags.conf` and `log.txt` files and specify the machine you were using.

After that, it's just a matter of waiting for the developers to do their work and answering the questions that they may have. Please, be patient.

**Caution:** Of course, there is a third option: you keep experiencing an error that appears randomly on some executions but you are not able to reproduce it in a consistent manner. Report it and attach as much logs and configuration files as you have, along with the date and time of the errors.



## DEVELOPER'S GUIDE

The tool provides a set of useful diagnostics, but a lot more can be required at anytime. If you miss something and are able to develop it, you are more than welcome to collaborate. Even if you can not develop it, please let us know what do you want.

The first step is to go to the GitLab page for the project ( [https://earth.bsc.es/gitlab/es/ocean\\_diagnostics/](https://earth.bsc.es/gitlab/es/ocean_diagnostics/) ) and open a new issue. Be sure that the title is self-explicative and give a detailed description of what you want. Please, be very explicit about what you want to avoid misunderstandings.

---

**Hint:** If reading your description, you think that you are taking the developers as stupids, you are doing it perfectly.

---

Don't forget to add the relevant tags. At this stage you will have to choose between 'enhancement', if you are proposing an improvement on a currently available feature, or 'new feature' in any the other case.

Now, if you are thinking on developing it yourself, please refer to the BSC-ES Git strategy ( [wiki\\_link\\_when\\_available](#) ) If you have any doubts, or just want help to start the development, contact [javier.vegas@bsc.es](mailto:javier.vegas@bsc.es).

### 6.1 Developing a diagnostic

For new diagnostics development, we have some advice to give:

- Do not worry about performance at first, just create a version that works. Developers can help you to optimize it later.
- There is nothing wrong with doing some common preparations in the `generate_jobs` of the diagnostic.
- Parallelization is achieved by running multiple diagnostics at a time. You don't need to implement it at diagnostic level
- Use the smallest time frame for your diagnostic: if you can work at chunk level, do not ask for full year data.
- Prefer NCO over CDO, you will have less problems when versions change.
- Ask for help as soon as you get stuck.
- Use always the methods in Utils instead of writing your own code.
- Use meaningful variable names. If you are using short names just to write less, please switch to an editor with autocompletion!
- Do not modify the mesh and mask files, another diagnostic can be using them at the same time.



## FREQUENTLY ASKED QUESTIONS

Here will be the answers to the most usual questions. For the moment, there is nothing to see here...



## MODULE DOCUMENTATION

### 8.1 earthdiagnostics

#### 8.1.1 earthdiagnostics.box

**class** earthdiagnostics.box.**Box** (*depth\_in\_meters=False*)

Bases: `object`

Represents a box in the 3D space. Also allows easy conversion from the coordinate values to significant string representations

**depth\_in\_meters = None**

If True, treats the depth as if it is given in meters. If False, as it is given in levels :rtype: bool

**get\_depth\_str()**

Gets a string representation of depth. For depth expressed in meters, it adds th character 'm' to the end  
If min\_depth is different from max\_depth, it concatenates the two values :return: string representation for depth :rtype: str

**get\_lat\_str()**

Gets a string representation of the latitude in the format XX{N/S}. If min\_lat is different from max\_lat, it concatenates the two values :return: string representation for latitude :rtype: str

**get\_lon\_str()**

Gets a string representation of the longitude in the format XX{E/W}. If min\_lon is different from max\_lon, it concatenates the two values :return: string representation for longitude :rtype: str

**max\_depth = None**

Maximum depth :rtype: float

**max\_lat**

Maximum latitude :rtype: float

**max\_lon**

Maximum longitude :rtype: float

**min\_depth = None**

Minimum depth :rtype: float

**min\_lat**

Minimum latitude :rtype: float

**min\_lon**

Minimum longitude :rtype: float

### 8.1.2 earthdiagnostics.cdftools

**class** earthdiagnostics.cdftools.CDFTools (*path*='')

Bases: `object`

Class to run CDFTools executables

**Parameters** *path* (*str*) – path to CDFTOOLS binaries

**run** (*command*, *input*, *output*=None, *options*=None, *log\_level*=20, *input\_option*=None)

Runs one of the CDFTools

**Parameters**

- **command** (*str* | *iterable*) – executable to run
- **input** (*str*) – input file
- **output** – output file. Not all tools support this parameter
- **options** (*str* | *list*[*str*] | *Tuple*[*str*]) – options for the tool.
- **log\_level** (*int*) – log level at which the output of the cdftool command will be added

### 8.1.3 earthdiagnostics.cmorizer

**class** earthdiagnostics.cmorizer.Cmorizer (*data\_manager*, *startdate*, *member*)

Bases: `object`

Class to manage CMORization

**Parameters**

- **data\_manager** (*CMORManager*) – experiment's data manager
- **startdate** (*str*) – startdate to cmorize
- **member** (*int*) – member to cmorize

**cmorize\_atmos** ()

CMORizes atmospheric data, from grib or MMA files :return:

**cmorize\_ocean** ()

CMORizes ocean files from MMO files :return:

**extract\_variable** (*file\_path*, *handler*, *frequency*, *variable*)

Extracts a variable from a file and creates the CMOR file

**Parameters**

- **file\_path** (*str*) – path to the file
- **handler** (*netCDF4.Dataset*) – netCDF4 handler for the file
- **frequency** (*Frequency*) – variable's frequency
- **variable** (*str*) – variable's name

### 8.1.4 earthdiagnostics.cmormanager

**class** earthdiagnostics.cmormanager.CMORManager (*config*)

Bases: `earthdiagnostics.datamanager.DataManager`

Data manager class for CMORized experiments

**get\_file** (*domain*, *var*, *startdate*, *member*, *chunk*, *grid=None*, *box=None*, *frequency=None*, *vartype=1*)

Copies a given file from the CMOR repository to the scratch folder and returns the path to the scratch's copy

#### Parameters

- **domain** (*Domain*) – CMOR domain
- **var** (*str*) – variable name
- **startdate** (*str*) – file's startdate
- **member** (*int*) – file's member
- **chunk** (*int*) – file's chunk
- **grid** (*str/NoneType*) – file's grid (only needed if it is not the original)
- **box** (*Box*) – file's box (only needed to retrieve sections or averages)
- **frequency** (*Frequency/NoneType*) – file's frequency (only needed if it is different from the default)
- **vartype** (*VariableType*) – Variable type (mean, statistic)

**Returns** path to the copy created on the scratch folder

#### Return type *str*

**get\_file\_path** (*startdate*, *member*, *domain*, *var*, *cmor\_var*, *chunk*, *frequency*, *grid=None*, *year=None*, *date\_str=None*)

Returns the path to a concrete file :param startdate: file's startdate :type startdate: str :param member: file's member :type member: int :param domain: file's domain :type domain: Domain :param var: file's var :type var: var :param chunk: file's chunk :type chunk: int :param frequency: file's frequency :type frequency: Frequency :param grid: file's grid :type grid: str|NoneType :param year: file's year :type year: int|str|NoneType :param date\_str: date string to add directly. Overrides year or chunk configurations :type date\_str: str|NoneType :return: path to the file :rtype: str|NoneType

**get\_year** (*domain*, *var*, *startdate*, *member*, *year*, *grid=None*, *box=None*)

Ge a file containing all the data for one year for one variable :param domain: variable's domain :type domain: str :param var: variable's name :type var: str :param startdate: startdate to retrieve :type startdate: str :param member: member to retrieve :type member: int :param year: year to retrieve :type year: int :param grid: variable's grid :type grid: str :param box: variable's box :type box: Box :return:

**link\_file** (*domain*, *var*, *cmor\_var*, *startdate*, *member*, *chunk=None*, *grid=None*, *frequency=None*, *year=None*, *date\_str=None*, *move\_old=False*, *vartype=1*)

Creates the link of a given file from the CMOR repository.

#### Parameters

- **move\_old** –
- **date\_str** –
- **year** (*int*) – if frequency is yearly, this parameter is used to give the corresponding year
- **domain** (*Domain*) – CMOR domain
- **var** (*str*) – variable name
- **startdate** (*str*) – file's startdate
- **member** (*int*) – file's member
- **chunk** (*int*) – file's chunk

- **grid** (*str*) – file’s grid (only needed if it is not the original)
- **frequency** (*Frequency*) – file’s frequency (only needed if it is different from the default)
- **vartype** (*VariableType*) – Variable type (mean, statistic)

**Returns** path to the copy created on the scratch folder

**Return type** *str*

**prepare** ()

Prepares the data to be used by the diagnostic.

If CMOR data is not created, it show a warning and closes. In the future, an automatic cmorization procedure will be launched

If CMOR data is available but packed, the procedure will unpack it.

**Returns**

**send\_file** (*filetosend*, *domain*, *var*, *startdate*, *member*, *chunk=None*, *grid=None*, *region=None*, *box=None*, *rename\_var=None*, *frequency=None*, *year=None*, *date\_str=None*, *move\_old=False*, *diagnostic=None*, *cmorized=False*, *vartype=1*)

Copies a given file to the CMOR repository. It also automatically converts to netCDF 4 if needed and can merge with already existing ones as needed

**Parameters**

- **move\_old** (*bool*) – if true, moves files following older conventions that may be found on the links folder
- **date\_str** – exact date\_str to use in the cmorized file
- **year** (*int*) – if frequency is yearly, this parameter is used to give the corresponding year
- **rename\_var** (*str*) – if exists, the given variable will be renamed to the one given by var
- **filetosend** (*str*) – path to the file to send to the CMOR repository
- **region** (*str*) – specifies the region represented by the file. If it is defined, the data will be appended to the CMOR repository as a new region in the file or will overwrite if region was already present
- **domain** (*Domain*) – CMOR domain
- **var** (*str*) – variable name
- **startdate** (*str*) – file’s startdate
- **member** (*int*) – file’s member
- **chunk** (*int*) – file’s chunk
- **grid** (*str*) – file’s grid (only needed if it is not the original)
- **box** (*Box*) – file’s box (only needed to retrieve sections or averages)
- **frequency** (*Frequency*) – file’s frequency (only needed if it is different from the default)
- **diagnostic** (*Diagnostic*) – diagnostic used to generate the file
- **cmorized** (*bool*) – flag to indicate if file was generated in cmorization process
- **vartype** (*VariableType*) – Variable type (mean, statistic)

Type `str`

### 8.1.5 earthdiagnostics.config

**class** `earthdiagnostics.config.Config`(*path*)

Bases: `object`

Class to read and manage the configuration

**Parameters** *path* (`str`) – path to the conf file

**cdftools\_path** = `None`

Path to CDFTOOLS executables

**con\_files** = `None`

Mask and meshes folder path

**data\_adaptor** = `None`

Scratch folder path

**data\_dir** = `None`

Root data folder path

**data\_type** = `None`

Data type (experiment, observation or reconstruction)

**experiment** = `None`

Configuration related to the experiment

**Return type** *ExperimentConfig*

**frequency** = `None`

Default data frequency to be used by the diagnostics

**get\_commands** ()

Returns the list of commands after replacing the alias :return: full list of commands :rtype: list(str)

**max\_cores** = `None`

Maximum number of cores to use

**restore\_meshes** = `None`

If True, forces the tool to copy all the mesh and mask files for the model, regardless of existence

**scratch\_dir** = `None`

Scratch folder path

**class** `earthdiagnostics.config.ExperimentConfig`(*parser*)

Bases: `object`

Encapsulates all chunk related tasks

**Parameters** *parser* (`Parser`) – parser for the config file

**get\_chunk\_list** ()

Return a list with all the chunks :return: List containing tuples of startdate, member and chunk :rtype: tuple[str, int, int]

**get\_full\_years** (*startdate*)

Returns the list of full years that are in the given startdate :param startdate: startdate to use :type startdate: str :return: list of full years :rtype: list[int]

**get\_member\_list** ()

Return a list with all the members :return: List containing tuples of startdate and member :rtype: tuple[str, int, int]

**get\_member\_str** (*member*)

Returns the member name for a given member number. :param member: member's number :type member: int :return: member's name :rtype: str

**get\_year\_chunks** (*startdate*, *year*)

Get the list of chunks containing timesteps from the given year :param startdate: startdate to use :type startdate: str :param year: reference year :type year: int :return: list of chunks containing data from the given year :rtype: list[int]

## 8.1.6 earthdiagnostics.constants

Contains the enumeration-like classes used by the diagnostics

**class** earthdiagnostics.constants.**Basin** (*shortname*, *fullname*, *box=None*)

Bases: `object`

Class representing a given basin

### Parameters

- **shortname** (*str*) – sfull basin's name
- **fullname** (*str*) – full basin's name
- **box** (`Box`) – box defining the basin

**box = None**

Box representing the basin

**fullname**

Basin's full name :rtype: str

**shortname**

Basin's short name :rtype: str

**class** earthdiagnostics.constants.**Basins**

Bases: `object`

Predefined basins

**Antarctic** = <earthdiagnostics.constants.Basin object>

Antarctic Ocean

**AntarcticAtlantic** = <earthdiagnostics.constants.Basin object>

Antarctic Ocean Atlantic Sector

**AntarcticIndian** = <earthdiagnostics.constants.Basin object>

Antarctic Ocean Indian Sector

**Arctic** = <earthdiagnostics.constants.Basin object>

Arctic Ocean

**ArcticMarginalSeas** = <earthdiagnostics.constants.Basin object>

Arctic Ocean

**ArcticNorthAtlantic** = <earthdiagnostics.constants.Basin object>

Arctic Ocean North Atlantic

**Atlantic** = <earthdiagnostics.constants.Basin object>  
Atlantic ocean

**Baffin** = <earthdiagnostics.constants.Basin object>  
Baffin

**Baffin\_Bay** = <earthdiagnostics.constants.Basin object>  
Baffin\_Bay

**Baltic\_Sea** = <earthdiagnostics.constants.Basin object>  
Baltic\_Sea

**BarKara** = <earthdiagnostics.constants.Basin object>  
BarKara

**Barents\_Sea** = <earthdiagnostics.constants.Basin object>  
Barents\_Sea

**Beaufort\_Chukchi\_Sea** = <earthdiagnostics.constants.Basin object>  
Beaufort\_Chukchi\_Sea

**Beaufort\_Sea** = <earthdiagnostics.constants.Basin object>  
Beaufort\_Sea

**Bellingshausen\_Sea** = <earthdiagnostics.constants.Basin object>  
Bellingshausen\_Sea

**Bering** = <earthdiagnostics.constants.Basin object>  
Bering

**Bering\_Strait** = <earthdiagnostics.constants.Basin object>  
Bering\_Strait

**CanArch** = <earthdiagnostics.constants.Basin object>  
CanArch

**Canadian\_Waters** = <earthdiagnostics.constants.Basin object>  
Canadian\_Waters

**Caspian\_Sea** = <earthdiagnostics.constants.Basin object>  
Caspian\_Sea

**Central\_Arctic** = <earthdiagnostics.constants.Basin object>  
Central\_Arctic

**Chukchi\_Sea** = <earthdiagnostics.constants.Basin object>  
Chukchi\_Sea

**East\_Siberian\_Sea** = <earthdiagnostics.constants.Basin object>  
East\_Siberian\_Sea

**Eastern\_Central\_Arctic** = <earthdiagnostics.constants.Basin object>  
Eastern\_Central\_Arctic

**Fram\_Strait** = <earthdiagnostics.constants.Basin object>  
Fram\_Strait

**Global** = <earthdiagnostics.constants.Basin object>  
Global ocean

**Global\_Ocean** = <earthdiagnostics.constants.Basin object>  
Global\_Ocean

**Greenland\_Sea** = <earthdiagnostics.constants.Basin object>  
Greenland\_Sea

**Grnland** = <earthdiagnostics.constants.Basin object>  
Grnland

**Hudson** = <earthdiagnostics.constants.Basin object>  
Hudson

**Icelandic\_Sea** = <earthdiagnostics.constants.Basin object>  
Icelandic\_Sea

**Indian** = <earthdiagnostics.constants.Basin object>  
Indian Ocean

**IndoPacific** = <earthdiagnostics.constants.Basin object>  
Indo Pacific Ocean

**Irminger\_Sea** = <earthdiagnostics.constants.Basin object>  
Irminger\_Sea

**Kara\_Gate\_Strait** = <earthdiagnostics.constants.Basin object>  
Kara\_Gate\_Strait

**Kara\_Sea** = <earthdiagnostics.constants.Basin object>  
Kara\_Sea

**Labrador\_Sea** = <earthdiagnostics.constants.Basin object>  
Labrador\_Sea

**Laptev\_East\_Siberian\_Chukchi\_Seas** = <earthdiagnostics.constants.Basin object>  
Laptev\_East\_Siberian\_Chukchi\_Seas

**Laptev\_East\_Siberian\_Seas** = <earthdiagnostics.constants.Basin object>  
Laptev\_East\_Siberian\_Seas

**Laptev\_Sea** = <earthdiagnostics.constants.Basin object>  
Laptev\_Sea

**Lincoln\_Sea** = <earthdiagnostics.constants.Basin object>  
Lincoln\_Sea

**Mediterranean\_Sea** = <earthdiagnostics.constants.Basin object>  
Mediterranean\_Sea

**Nares\_Strait** = <earthdiagnostics.constants.Basin object>  
Nares\_Strait

**Nordic\_Barents\_Seas** = <earthdiagnostics.constants.Basin object>  
Nordic\_Barents\_Seas

**Nordic\_Seas** = <earthdiagnostics.constants.Basin object>  
Nordic\_Seas

**NorthAtlantic** = <earthdiagnostics.constants.Basin object>  
North Atlantic Ocean

**NorthPacific** = <earthdiagnostics.constants.Basin object>  
North Pacific Ocean

**NorthWest\_Passage** = <earthdiagnostics.constants.Basin object>  
NorthWest\_Passage

**North\_Atlantic\_Arctic** = <earthdiagnostics.constants.Basin object>  
 North\_Atlantic\_Arctic

**North\_Hemisphere\_Ocean** = <earthdiagnostics.constants.Basin object>  
 North\_Hemisphere\_Ocean

**Norwegian\_Sea** = <earthdiagnostics.constants.Basin object>  
 Norwegian\_Sea

**Okhotsk** = <earthdiagnostics.constants.Basin object>  
 Okhotsk

**OpenOcean** = <earthdiagnostics.constants.Basin object>  
 OpenOcean

**Pacific** = <earthdiagnostics.constants.Basin object>  
 Pacific Ocean

**Ross\_Sea** = <earthdiagnostics.constants.Basin object>  
 Ross\_Sea

**Serreze\_Arctic** = <earthdiagnostics.constants.Basin object>  
 Serreze\_Arctic

**Southern\_Hemisphere** = <earthdiagnostics.constants.Basin object>  
 Southern\_Hemisphere

**StLawr** = <earthdiagnostics.constants.Basin object>  
 StLawr

**Subpolar\_Gyre** = <earthdiagnostics.constants.Basin object>  
 Subpolar\_Gyre

**TotalArc** = <earthdiagnostics.constants.Basin object>  
 TotalArc

**TropicalAtlantic** = <earthdiagnostics.constants.Basin object>  
 Tropical Atlantic Ocean

**TropicalIndian** = <earthdiagnostics.constants.Basin object>  
 Tropical Indian Ocean

**TropicalPacific** = <earthdiagnostics.constants.Basin object>  
 Tropical Pacific Ocean

**Vilkitsky\_Strait** = <earthdiagnostics.constants.Basin object>  
 Vilkitsky\_Strait

**Weddell\_Sea** = <earthdiagnostics.constants.Basin object>  
 Weddell\_Sea

**Western\_Central\_Arctic** = <earthdiagnostics.constants.Basin object>  
 Western\_Central\_Arctic

**classmethod parse** (*basin*)

Return the basin matching the given name. If the parameter *basin* is a *Basin* instance, directly returns the same instance. This behaviour is intended to facilitate the development of methods that can either accept a name or a *Basin* instance to characterize the basin.

**Parameters** *basin* (*str* | *Basin*) – basin name or basin instance

**Returns** basin instance corresponding to the basin name

**Return type** *Basin*

```
class earthdiagnostics.constants.Models
    Bases: object

    Predefined models

    ECEARTH_2_3_O1L42 = 'Ec2.3_O1L42'
        EC-Earth 2.3 ORCA1 L42

    ECEARTH_3_0_O1L46 = 'Ec3.0_O1L46'
        EC-Earth 3 ORCA1 L46

    ECEARTH_3_0_O25L46 = 'Ec3.0_O25L46'
        EC-Earth 3 ORCA0.25 L46

    ECEARTH_3_0_O25L75 = 'Ec3.0_O25L75'
        EC-Earth 3 ORCA0.25 L75

    ECEARTH_3_1_O25L75 = 'Ec3.1_O25L75'
        EC-Earth 3.1 ORCA0.25 L75

    ECEARTH_3_2_O1L75 = 'Ec3.2_O1L75'
        EC-Earth 3.2 ORCA1 L75

    GLORYS2_V1_O25L75 = 'glorys2v1_O25L75'
        GLORYS2v1 ORCA0.25 L75

    NEMOVAR_O1L42 = 'nemovar_O1L42'
        NEMOVAR ORCA1 L42

    NEMO_3_2_O1L42 = 'N3.2_O1L42'
        NEMO 3.2 ORCA1 L42

    NEMO_3_3_O1L46 = 'N3.3_O1L46'
        NEMO 3.3 ORCA1 L46

    NEMO_3_6_O1L46 = 'N3.6_O1L75'
        NEMO 3.6 ORCA1 L75
```

### 8.1.7 earthdiagnostics.datamanager

```
class earthdiagnostics.datamanager.DataManager (config)
    Bases: object

    Class to manage the data repositories

    Parameters config (Config) –

    file_exists (domain, var, startdate, member, chunk, grid=None, box=None, frequency=None, var-
        type=1)
        Checks if a given file exists

    Parameters

    • domain (Domain) – CMOR domain

    • var (str) – variable name

    • startdate (str) – file's startdate

    • member (int) – file's member

    • chunk (int) – file's chunk

    • grid (str) – file's grid (only needed if it is not the original)
```

- **box** (*Box*) – file’s box (only needed to retrieve sections or averages)
- **frequency** (*Frequency*) – file’s frequency (only needed if it is different from the default)
- **vartype** (*VariableType*) – Variable type (mean, statistic)

**Returns** path to the copy created on the scratch folder

**Return type** *str*

**get\_file** (*domain, var, startdate, member, chunk, grid=None, box=None, frequency=None, vartype=1*)

Copies a given file from the CMOR repository to the scratch folder and returns the path to the scratch’s copy

#### Parameters

- **domain** (*Domain*) – CMOR domain
- **var** (*str*) – variable name
- **startdate** (*str*) – file’s startdate
- **member** (*int*) – file’s member
- **chunk** (*int*) – file’s chunk
- **grid** (*str*) – file’s grid (only needed if it is not the original)
- **box** (*Box*) – file’s box (only needed to retrieve sections or averages)
- **frequency** (*Frequency*) – file’s frequency (only needed if it is different from the default)
- **vartype** (*VariableType*) – Variable type (mean, statistic)

**Returns** path to the copy created on the scratch folder

**Return type** *str*

**get\_year** (*domain, var, startdate, member, year, grid=None, box=None*)

Ge a file containing all the data for one year for one variable :param domain: variable’s domain :type domain: Domain :param var: variable’s name :type var: str :param startdate: startdate to retrieve :type startdate: str :param member: member to retrieve :type member: int :param year: year to retrieve :type year: int :param grid: variable’s grid :type grid: str :param box: variable’s box :type box: Box :return:

**link\_file** (*domain, var, cmor\_var, startdate, member, chunk=None, grid=None, frequency=None, year=None, date\_str=None, move\_old=False, vartype=1*)

Creates the link of a given file from the CMOR repository.

#### Parameters

- **cmor\_var** –
- **move\_old** –
- **date\_str** –
- **year** (*int*) – if frequency is yearly, this parameter is used to give the corresponding year
- **domain** (*Domain*) – CMOR domain
- **var** (*str*) – variable name
- **startdate** (*str*) – file’s startdate
- **member** (*int*) – file’s member

- **chunk** (*int*) – file’s chunk
- **grid** (*str*) – file’s grid (only needed if it is not the original)
- **frequency** (*str*) – file’s frequency (only needed if it is different from the default)
- **vartype** (*VariableType*) – Variable type (mean, statistic)

**Returns** path to the copy created on the scratch folder

**Return type** *str*

**prepare** ()

Prepares the data to be used by the diagnostic. :return:

**send\_file** (*filetosend*, *domain*, *var*, *startdate*, *member*, *chunk=None*, *grid=None*, *region=None*, *box=None*, *rename\_var=None*, *frequency=None*, *year=None*, *date\_str=None*, *move\_old=False*, *diagnostic=None*, *cmorized=False*, *vartype=1*)

Copies a given file to the CMOR repository. It also automatically converts to netCDF 4 if needed and can merge with already existing ones as needed

**Parameters**

- **move\_old** (*bool*) – if true, moves files following older conventions that may be found on the links folder
- **date\_str** – exact date\_str to use in the cmorized file
- **year** (*int*) – if frequency is yearly, this parameter is used to give the corresponding year
- **rename\_var** (*str*) – if exists, the given variable will be renamed to the one given by var
- **filetosend** (*str*) – path to the file to send to the CMOR repository
- **region** (*str*) – specifies the region represented by the file. If it is defined, the data will be appended to the CMOR repository as a new region in the file or will overwrite if region was already present
- **domain** (*Domain*) – CMOR domain
- **var** (*str*) – variable name
- **startdate** (*str*) – file’s startdate
- **member** (*int*) – file’s member
- **chunk** (*int*) – file’s chunk
- **grid** (*str*) – file’s grid (only needed if it is not the original)
- **box** (*Box*) – file’s box (only needed to retrieve sections or averages)
- **frequency** (*Frequency*) – file’s frequency (only needed if it is different from the default)
- **diagnostic** (*Diagnostic*) – diagnostic used to generate the file
- **cmorized** (*bool*) – flag to indicate if file was generated in cmorization process
- **vartype** (*VariableType*) – Variable type (mean, statistic)

**Type** *str*

**class** earthdiagnostics.datamanager.**NetCDFFile** (*remote\_file*, *local\_file*, *domain*, *var*, *cmor\_var*, *data\_convention*, *region*)

Bases: *object*

Class to manage netCDF file and pr

#### Parameters

- **remote\_file** (*str*) –
- **local\_file** (*str*) –
- **domain** (*Domain*) –
- **var** (*str*) –
- **cmor\_var** (*Variable*) –

**class** earthdiagnostics.datamanager.**UnitConversion** (*source, destiny, factor, offset*)

Bases: `object`

Class to manage unit conversions

**classmethod** **add\_conversion** (*conversion*)

Adds a conversion to the dictionary

**Parameters** **conversion** (*UnitConversion*) – conversion to add

**classmethod** **get\_conversion\_factor\_offset** (*input\_units, output\_units*)

Gets the conversion factor and offset for two units . The conversion has to be done in the following way:  
converted = original \* factor + offset

#### Parameters

- **input\_units** (*str*) – original units
- **output\_units** (*str*) – destiny units

**Returns** factor and offset

**Return type** [float, float]

**classmethod** **load\_conversions** ()

Load conversions from the configuration file

## 8.1.8 earthdiagnostics.diagnostic

**class** earthdiagnostics.diagnostic.**Diagnostic** (*data\_manager*)

Bases: `object`

Base class for the diagnostics. Provides a common interface for them and also has a mechanism that allows diagnostic retrieval by name.

**Parameters** **data\_manager** (*DataManager*) – data manager that will be used to store and retrieve the necessary data

**alias** = `None`

Alias to call the diagnostic. Must be overridden at the derived classes

**compute** ()

Calculates the diagnostic and stores the output

Must be implemented by derived classes

**classmethod** **generate\_jobs** (*diags, options*)

Generate the instances of the diagnostics that will be run by the manager

Must be implemented by derived classes.

#### Parameters

- **diags** (*Diags*) – diagnostics manager
- **options** (*list[str]*) – list of strings containing the options passed to the diagnostic

**Returns**

**static get\_diagnostic** (*name*)

Return the class for a diagnostic given its name

**Parameters** **name** (*str*) – diagnostic alias

**Returns** the selected Diagnostic class, None if name can not be found

**Return type** *Diagnostic*

**static register** ()

Register a new diagnostic using the given alias. It must be call using the derived class. :param cls: diagnostic class to register :type cls: Diagnostic

**send\_file** (*filetosend, domain, var, startdate, member, chunk=None, grid=None, region=None, box=None, rename\_var=None, frequency=None, year=None, date\_str=None, move\_old=False, vartype=1*)

**Parameters**

- **filetosend** –
- **domain** (*ModelingRealm*) –
- **var** –
- **startdate** –
- **member** –
- **chunk** –
- **grid** –
- **region** –
- **box** –
- **rename\_var** –
- **frequency** (*Frequency*) –
- **year** –
- **date\_str** –
- **move\_old** –
- **vartype** (*VariableType*) – Variable type (mean, statistic)

**Returns**

### 8.1.9 earthdiagnostics.earthdiags

**class** earthdiagnostics.earthdiags.**EarthDiags** (*config\_file*)

Bases: *object*

Launcher class for the diagnostics

**Parameters** **config\_file** (*str*) – path to the configuration file

**static parse\_args()**

Entry point for the Earth Diagnostics. For more detailed documentation, use -h option

**run()**

Run the diagnostics

### 8.1.10 earthdiagnostics.parser

**class** earthdiagnostics.parser.**Parser** (defaults=None, dict\_type=<class 'collections.OrderedDict'>, allow\_no\_value=False)  
 Bases: ConfigParser.SafeConfigParser

Class to manage the config file. It add options to manage default values and to convert strings to the desired types (int, bool, list ...)

**add\_section** (section)

Create a new section in the configuration.

Raise DuplicateSectionError if a section by the specified name already exists. Raise ValueError if name is DEFAULT or any of it's case-insensitive variants.

**check\_exists** (section, option)

Checks if an option exists

**Parameters**

- **section** (str) – section that contains the option
- **option** (str) – option to check

**Returns** True if option exists, False otherwise

**Return type** bool

**check\_is\_boolean** (section, option, must\_exist)

Checks if an option is a boolean value

**Parameters**

- **section** (str) – section that contains the option
- **option** (str) – option to check
- **must\_exist** (bool) – if True, option must exist

**Returns** True if option value is boolean, False otherwise

**Return type** bool

**check\_is\_choice** (section, option, must\_exist, choices)

Checks if an option is a valid choice in given self

**Parameters**

- **section** (str) – section that contains the option
- **option** (str) – option to check
- **must\_exist** (bool) – if True, option must exist
- **choices** (list) – valid choices

**Returns** True if option value is a valid choice, False otherwise

**Return type** bool

**check\_is\_int** (*section, option, must\_exist*)

Checks if an option is an integer value

**Parameters**

- **section** (*str*) – section that contains the option
- **option** (*str*) – option to check
- **must\_exist** (*bool*) – if True, option must exist

**Returns** True if option value is integer, False otherwise

**Return type** `bool`

**check\_regex** (*section, option, must\_exist, regex*)

Checks if an option complies with a regular expression

**Parameters**

- **section** (*str*) – section that contains the option
- **option** (*str*) – option to check
- **must\_exist** (*bool*) – if True, option must exist
- **regex** (*str*) – regular expression to check

**Returns** True if option complies with regex, False otherwise

**Return type** `bool`

**get** (*section, option, raw=False, vars=None*)

Get an option value for a given section.

If ‘vars’ is provided, it must be a dictionary. The option is looked up in ‘vars’ (if provided), ‘section’, and in ‘defaults’ in that order.

All % interpolations are expanded in the return values, unless the optional argument ‘raw’ is true. Values for interpolation keys are looked up in the same manner as the option.

The section DEFAULT is special.

**get\_bool\_option** (*section, option, default=True*)

Gets a boolean option

**Parameters**

- **section** (*str*) – section that contains the option
- **option** (*str*) – option to get
- **default** (*bool*) – value to be returned if option is not present

**Returns** option value

**Return type** `bool`

**get\_float\_option** (*section, option, default=0.0*)

Gets a float option

**Parameters**

- **section** (*str*) – section that contains the option
- **option** (*str*) – option to get
- **default** (*float*) – value to be returned if option is not present

**Returns** option value

**Return type** `float`

**get\_int\_option** (*section*, *option*, *default*=0)

Gets an integer option

**Parameters**

- **section** (*str*) – section that contains the option
- **option** (*str*) – option to get
- **default** (*int*) – value to be returned if option is not present

**Returns** option value

**Return type** `int`

**get\_list\_option** (*section*, *option*, *default*=[], *separator*= ' ')

Gets a list option

**Parameters**

- **section** (*str*) – section that contains the option
- **option** (*str*) – option to get
- **default** (*object*) – value to be returned if option is not present
- **separator** (*str*) – separator used to split the list

**Returns** option value

**Return type** `list`

**get\_option** (*section*, *option*, *default*='')

Gets an option

**Parameters**

- **section** (*str*) – section that contains the option
- **option** (*str*) – option to get
- **default** (*object*) – value to be returned if option is not present

**Returns** option value

**Return type** `str`

**has\_option** (*section*, *option*)

Check for the existence of a given option in a given section.

**has\_section** (*section*)

Indicate whether the named section is present in the configuration.

The DEFAULT section is not acknowledged.

**items** (*section*, *raw*=False, *vars*=None)

Return a list of tuples with (name, value) for each option in the section.

All % interpolations are expanded in the return values, based on the defaults passed into the constructor, unless the optional argument 'raw' is true. Additional substitutions may be provided using the 'vars' argument, which must be a dictionary whose contents overrides any pre-existing defaults.

The section DEFAULT is special.

**options** (*section*)

Return a list of option names for the given section name.

**read** (*filenames*)

Read and parse a filename or a list of filenames.

Files that cannot be opened are silently ignored; this is designed so that you can specify a list of potential configuration file locations (e.g. current directory, user's home directory, systemwide directory), and all existing configuration files in the list will be read. A single filename may also be given.

Return list of successfully read files.

**readfp** (*fp*, *filename=None*)

Like read() but the argument must be a file-like object.

The 'fp' argument must have a 'readline' method. Optional second argument is the 'filename', which if not given, is taken from fp.name. If fp has no 'name' attribute, '<???' is used.

**remove\_option** (*section*, *option*)

Remove an option.

**remove\_section** (*section*)

Remove a file section.

**sections** ()

Return a list of section names, excluding [DEFAULT]

**set** (*section*, *option*, *value=None*)

Set an option. Extend ConfigParser.set: check for string values.

**write** (*fp*)

Write an .ini-format representation of the configuration state.

## 8.1.11 earthdiagnostics.utils

**class** earthdiagnostics.utils.TempFile

Bases: `object`

Class to manage temporal files

**autoclean** = **True**

If True, new temporary files are added to the list for future cleaning

**static clean** ()

Removes all temporary files created with Tempfile until now

**files** = []

List of files to clean automatically

**static get** (*filename=None*, *clean=None*, *suffix='.nc'*)

Gets a new temporal filename, storing it for automated cleaning

**Parameters**

- **suffix** –
- **filename** (*str*) – if it is not none, the function will use this filename instead of a random one
- **clean** (*bool*) – if true, stores filename for cleaning

**Returns** path to the temporal file

**Return type** `str`

```

prefix = 'temp'
    Prefix for temporary filenames

scratch_folder = ''
    Scratch folder to create temporary files on it

```

**class** earthdiagnostics.utils.Utills

Bases: `object`

Container class for miscellaneous utility methods

**exception** ExecutionError

Bases: `exceptions.Exception`

Exception to raise when a command execution fails

**exception** Utills.UnzipException

Bases: `exceptions.Exception`

Excpetion raised when unzip fails

**static** Utills.available\_cpu\_count()

Number of available virtual or physical CPUs on this systemx

Utills.cdo = <cdo.Cdo object>

An instance of Cdo class ready to be used

**static** Utills.concat\_variables(source, destiny, remove\_source=False)

Add variables from a nc file to another :param source: path to source file :type source: str :param destiny: path to destiny file :type destiny: str :param remove\_source: if True, removes source file :type remove\_source: bool

**static** Utills.convert2netcdf4(filetoconvert)

Checks if a file is in netCDF4 format and converts to netCDF4 if not

**Parameters** filetoconvert (*str*) – file to convert

**static** Utills.copy\_dimension(source, destiny, dimension, must\_exist=True, new\_names=None)

Copies the given dimension from source to destiny, including dimension variables if present

**Parameters**

- **new\_names** (*dict*) – dictionary containing variables to rename and new name as key-value pairs
- **source** (*netCDF4.Dataset*) – origin file
- **destiny** (*netCDF4.Dataset*) – destiny file
- **dimension** (*str*) – variable to copy
- **must\_exist** (*bool*) – if false, does not raise an error uf variable does not exist

**Returns**

**static** Utills.copy\_file(source, destiny)

Copies a file from source to destiny, creating dirs if necessary

**Parameters**

- **source** (*str*) – path to source
- **destiny** (*str*) – path to destiny

**static** Utills.copy\_variable(source, destiny, variable, must\_exist=True, add\_dimensions=False, new\_names=None)

Copies the given variable from source to destiny

**Parameters**

- **add\_dimensions** (*bool*) – if it's true, dimensions required by the variable will be automatically added to the file. It will also add the dimension variable
- **source** (*netCDF4.Dataset*) – origin file
- **destiny** (*netCDF4.Dataset*) – destiny file
- **variable** (*str*) – variable to copy
- **must\_exist** (*bool*) – if false, does not raise an error if variable does not exist
- **new\_names** (*dict*) – dictionary containing variables to rename and new name as key-value pairs

**Returns**

**static** `Utils.create_folder_tree(path)`

Creates a folder path with all parent directories if needed. :param path: folder's path :type path: str

**static** `Utils.execute_shell_command(command, log_level=10)`

Executes a shell command :param command: command to execute

Log.info('Detailed time for diagnostic class') :param log\_level: log level to use for command output :type log\_level: int :return: command output :rtype: list

**static** `Utils.expand_path(path)`

Expands character ~ and system variables on the given path :param path: path to expand :type path: str :return: path after the expansion

**static** `Utils.get_datetime_from_netcdf(handler, time_variable='time')`

Gets a datetime array from a netCDF file

**Parameters**

- **handler** (*netCDF4.Dataset*) – file to read
- **time\_variable** (*str*) – variable to read, by default 'time'

**Returns** Datetime numpy array created from the values stored at the netCDF file

**Return type** np.array

**static** `Utils.get_file_hash(filepath)`

Returns the MD5 hash for the given filepath :param filepath: path to the file to compute hash on :type filepath: str :return: file's MD5 hash :rtype: str

**static** `Utils.get_mask(basin)`

Returns a numpy array containing the mask for the given basin

**Parameters** **basin** (*Basin*) – basin to retrieve

**Returns** mask

**Return type** numpy.array

**static** `Utils.move_file(source, destiny)`

Moves a file from source to destiny, creating dirs if necessary

**Parameters**

- **source** (*str*) – path to source
- **destiny** (*str*) – path to destiny

`Utils.nco = <nco.nco.Nco object>`

An instance of Nco class ready to be used

**static** `Utils.openCdf(filepath, mode='a')`

Opens a netCDF file and returns a handler to it

**Parameters**

- **filepath** (*str*) – path to the file
- **mode** (*str*) – mode to open the file. By default, a (append)

**Returns** handler to the file

**Return type** netCDF4.Dataset

**static** `Utils.remove_file(path)`

Removes a file, checking before if its exists

**Parameters** **path** (*str*) – path to file

**static** `Utils.rename_variable(filepath, old_name, new_name, must_exist=True, rename_dimension=False)`

Rename multiple variables from a NetCDF file :param filepath: path to file :type filepath: str :param old\_name: variable's name to change :type old\_name: str :param new\_name: new name :type new\_name: str :param must\_exist: if True, the function will raise an exception if the variable name does not exist :type must\_exist: bool :param rename\_dimension: if True, also rename dimensions with the same name :type rename\_dimension: bool

**static** `Utils.rename_variables(filepath, dic_names, must_exist=True, rename_dimension=False)`

Rename multiple variables from a NetCDF file :param filepath: path to file :type filepath: str :param dic\_names: dictionary containing old names as keys and new names as values :type dic\_names: dict :param must\_exist: if True, the function will raise an exception if the variable name does not exist :type must\_exist: bool :param rename\_dimension: if True, also rename dimensions with the same name :type rename\_dimension: bool

**static** `Utils.setminmax(filename, variable_list)`

Sets the valid\_max and valid\_min values to the current max and min values on the file :param filename: path to file :type filename: str :param variable\_list: list of variables in which valid\_min and valid\_max will be set :type variable\_list: str | list

**static** `Utils.untar(files, destiny_path)`

Untar files to a given destiny :param files: files to unzip :type files: list[Any] | Tuple[Any] :param destiny\_path: path to destination folder :type destiny\_path: str

**static** `Utils.unzip(files, force=False)`

Unzip a list of files :param files: files to unzip :type files: list | str :param force: if True, it will overwrite unzipped files :type force: bool

## 8.1.12 earthdiagnostics.variable

**class** `earthdiagnostics.variable.Variable`

Bases: `object`

Class to characterize a CMOR variable. It also contains the static method to make the match between the original name and the standard name. Requires data\_convention to be available in cmor\_tables to work.

**class** `earthdiagnostics.variable.VariableAlias(alias)`

Bases: `object`

Class to characterize a CMOR variable. It also contains the static method to make the match between the original name and the standard name. Requires `data_convention` to be available in `cmor_tables` to work.

## 8.2 earthdiagnostics.general

### 8.2.1 earthdiagnostics.general.attribute

**class** `earthdiagnostics.general.attribute.Attribute` (*data\_manager, startdate, member, chunk, domain, variable, grid, attribute\_name, attribute\_value*)

Bases: `earthdiagnostics.diagnostic.Diagnostic`

Rewrites files without doing any calculations. Can be useful to convert units or to correct wrong metadata

**Original author** Javier Vegas-Regidor<[javier.vegas@bsc.es](mailto:javier.vegas@bsc.es)>

**Created** July 2016

#### Parameters

- **data\_manager** (`DataManager`) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **variable** (*str*) – variable’s name
- **domain** (`ModelingRealm`) – variable’s domain

**alias** = ‘att’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, domain, grid

#### Returns

### 8.2.2 earthdiagnostics.general.monthlymean

**class** `earthdiagnostics.general.monthlymean.MonthlyMean` (*data\_manager, startdate, member, chunk, domain, variable, frequency, grid*)

Bases: `earthdiagnostics.diagnostic.Diagnostic`

Calculates monthly mean for a given variable

**Original author** Javier Vegas-Regidor<[javier.vegas@bsc.es](mailto:javier.vegas@bsc.es)>

**Created** July 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **variable** (*str*) – variable’s name
- **domain** (*ModelingRealm*) – variable’s domain
- **frequency** (*str*) – original frequency
- **grid** (*str*) – original data grid

**alias** = ‘monmean’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, domain, frequency=day, grid=’

**Returns**

### 8.2.3 earthdiagnostics.general.relink

**class** earthdiagnostics.general.relink.**Relink** (*data\_manager, startdate, member, chunk, domain, variable, move\_old, grid*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Recreates the links for the variable specified

**Original author** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** September 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **variable** (*str*) – variable’s name
- **domain** (*ModelingRealm*) – variable’s domain
- **move\_old** (*bool*) – if true, looks for files following the old convention and moves to avoid collisions

**alias** = ‘relink’

Diagnostic alias for the configuration file

**compute()**

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, domain, move\_old=False

**Returns**

## 8.2.4 earthdiagnostics.general.relinkall

**class** earthdiagnostics.general.relinkall.**RelinkAll** (*data\_manager, startdate*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Recreates the links for the variable specified

**Original author** Javier Vegas-Regidor<[javier.vegas@bsc.es](mailto:javier.vegas@bsc.es)>

**Created** September 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate

**alias** = 'relinkall'

Diagnostic alias for the configuration file

**compute()**

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, domain, move\_old=False

**Returns**

## 8.2.5 earthdiagnostics.general.rewrite

**class** earthdiagnostics.general.rewrite.**Rewrite** (*data\_manager, startdate, member, chunk,*  
*domain, variable, grid*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Rewrites files without doing any calculations. Can be useful to convert units or to correct wrong metadata

**Original author** Javier Vegas-Regidor<[javier.vegas@bsc.es](mailto:javier.vegas@bsc.es)>

**Created** July 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object

- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **variable** (*str*) – variable’s name
- **domain** (*ModelingRealm*) – variable’s domain

**alias** = ‘rewrite’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, domain, grid

**Returns**

## 8.2.6 earthdiagnostics.general.scale

**class** earthdiagnostics.general.scale.**Scale** (*data\_manager, startdate, member, chunk, value, offset, domain, variable, grid, min\_limit, max\_limit*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Scales a variable by the given value also adding at offset Can be useful to correct units or other known errors (think of a tas file declaring K as units but with the data stored as Celsius)

**Original author** Javier Vegas-Regidor<[javier.vegas@bsc.es](mailto:javier.vegas@bsc.es)>

**Created** July 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int* : ) – chunk’s number
- **variable** (*str*) – variable’s name
- **domain** (*ModelingRealm*) – variable’s domain

**alias** = ‘scale’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, domain, grid

Returns

## 8.3 earthdiagnostics.ocean

### 8.3.1 earthdiagnostics.ocean.areamoc

**class** earthdiagnostics.ocean.areamoc.**AreaMoc** (*data\_manager*, *startdate*, *member*, *chunk*,  
*basin*, *box*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Compute an Atlantic MOC index by averaging the meridional overturning in a latitude band between 1km and 2km or any other index averaging the meridional overturning in a given basin and a given domain

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** March 2012

**Last modified** June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **basin** (*Basin*) – basin to compute
- **box** (*Box*) – box to compute

**alias** = ‘mocarea’

Diagnostics alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags*, *options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – minimum latitude, maximum latitude, minimum depth, maximum depth, basin=Global

Returns

### 8.3.2 earthdiagnostics.ocean.averagesection

**class** earthdiagnostics.ocean.averagesection.**AverageSection** (*data\_manager, startdate, member, chunk, domain, variable, box*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Compute an average of a given zone. The variable MUST be in a regular grid

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** March 2012

**Last modified** June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **variable** (*str*) – variable’s name
- **domain** (*ModelingRealm*) – variable’s domain
- **box** (*Box*) – box to use for the average

**alias** = ‘avgsection’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, minimum longitude, maximum longitude, minimum latitude, maximum latitude, domain=ocean

#### Returns

### 8.3.3 earthdiagnostics.ocean.convectionsites

**class** earthdiagnostics.ocean.convectionsites.**ConvectionSites** (*data\_manager, start-date, member, chunk, model\_version*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Compute the intensity of convection in the four main convection sites

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** October 2013

Last modified June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **model\_version** (*str*) – model version

**alias** = ‘convection’

Dagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – None

#### Returns

### 8.3.4 earthdiagnostics.ocean.cutsection

**class** earthdiagnostics.ocean.cutsection.**CutSection** (*data\_manager, startdate, member, chunk, domain, variable, zonal, value*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Cuts a meridional or zonal section

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** September 2012

**Last modified** June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **variable** (*str*) – variable’s name
- **domain** (*Domain*) – variable’s domain
- **zonal** (*bool*) – specifies if section is zonal or meridional
- **value** (*int*) – value of the section’s coordinate

**alias = 'cutsection'**

Diagnostic alias for the configuration file

**compute ()**

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, zonal, value, domain=ocean

#### Returns

### 8.3.5 earthdiagnostics.ocean.gyres

**class** earthdiagnostics.ocean.gyres.**Gyres** (*data\_manager, startdate, member, chunk, model\_version*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Compute the intensity of the subtropical and subpolar gyres

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** October 2013

**Last modified** June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk's number
- **model\_version** (*str*) – model version

**alias = 'gyres'**

Diagnostic alias for the configuration file

**compute ()**

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – None

#### Returns

### 8.3.6 earthdiagnostics.ocean.heatcontent

**class** earthdiagnostics.ocean.heatcontent.**HeatContent** (*data\_manager, startdate, member, chunk, basin, mixed\_layer, box*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Compute the total ocean heat content

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** May 2012

**Last modified** June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **mixed\_layer** (*int*) – If 1, restricts calculation to the mixed layer, if -1 exclude it. If 0, no effect
- **box** (*Box*) – box to use for the average

**alias** = ‘ohc’

Dagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – basin, mixed layer option (1 to only compute at the mixed layer, -1 to exclude it, 0 to ignore), minimum depth, maximum depth

#### Returns

### 8.3.7 earthdiagnostics.ocean.heatcontentlayer

**class** earthdiagnostics.ocean.heatcontentlayer.**HeatContentLayer** (*data\_manager, startdate, member, chunk, box, weight, min\_level, max\_level*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Point-wise Ocean Heat Content in a specified ocean thickness (J/m-2)

**Original author** Isabel Andreu Burillo

**Contributor** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Eleftheria Exarchou <eleftheria.exarchou@bsc.es>

**Contributor** Javier Vegas-Regidor<[javier.vegas@bsc.es](mailto:javier.vegas@bsc.es)>

**Created** June 2012

**Last modified** June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **box** (*Box*) – box to use for the calculations

**alias** = ‘ohclayer’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – minimum depth, maximum depth, basin=Global

### 8.3.8 earthdiagnostics.ocean.interpolate

```
class earthdiagnostics.ocean.interpolate.Interpolate(data_manager, startdate, member, chunk, domain, variable, target_grid, model_version, invert_lat)
```

Bases: *earthdiagnostics.diagnostic.Diagnostic*

3-dimensional conservative interpolation to the regular atmospheric grid. It can also be used for 2D (i,j) variables

**Original author** Virginie Guemas <[virginie.guemas@bsc.es](mailto:virginie.guemas@bsc.es)>

**Contributor** Javier Vegas-Regidor<[javier.vegas@bsc.es](mailto:javier.vegas@bsc.es)>

**Created** November 2012

**Last modified** June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **variable** (*str*) – variable’s name
- **domain** (*Domain*) – variable’s domain
- **model\_version** (*str*) – model version

**alias = 'interp'**

Diagnostics alias for the configuration file

**compute()**

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – target\_grid, variable, domain=ocean

**Returns**

### 8.3.9 earthdiagnostics.ocean.interpolatecdo

```
class earthdiagnostics.ocean.interpolatecdo.InterpolateCDO(data_manager, start-date, member, chunk, domain, variable, target_grid, model_version, mask_oceans)
```

Bases: *earthdiagnostics.diagnostic.Diagnostic*

3-dimensional conservative interpolation to the regular atmospheric grid. It can also be used for 2D (i,j) variables

**Original author** Javier Vegas-Regidor<[javier.vegas@bsc.es](mailto:javier.vegas@bsc.es)>

**Created** October 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk's number
- **variable** (*str*) – variable's name
- **domain** (*ModelingRealm*) – variable's domain
- **model\_version** (*str*) – model version

**alias = 'interpcdo'**

Diagnostics alias for the configuration file

**compute()**

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – target\_grid, variable, domain=ocean

**Returns**

### 8.3.10 earthdiagnostics.ocean.maxmoc

**class** earthdiagnostics.ocean.maxmoc.**MaxMoc** (*data\_manager, startdate, member, year, basin, box*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Compute an Atlantic MOC index by finding the maximum of the annual mean meridional overturning in a latitude / depth region

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** March 2012

**Last modified** June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **year** (*int*) – year to compute
- **basin** (*Basin*) – basin to compute
- **box** (*Box*) – box to compute

**alias** = 'mocmax'

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each complete year to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – minimum latitude, maximum latitude, minimum depth, maximum depth, basin=global

#### Returns

### 8.3.11 earthdiagnostics.ocean.mixedlayerheatcontent

**class** earthdiagnostics.ocean.mixedlayerheatcontent.**MixedLayerHeatContent** (*data\_manager, start-date, member, chunk*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Compute mixed layer heat content

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** February 2012

**Last modified** June 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number

**alias** = ‘mlotsthc’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – None

**Returns**

### 8.3.12 earthdiagnostics.ocean.mixedlayersaltcontent

```
class earthdiagnostics.ocean.mixedlayersaltcontent.MixedLayerSaltContent (data_manager,  
                                                                           start-  
                                                                           date,  
                                                                           mem-  
                                                                           ber,  
                                                                           chunk)
```

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Compute mixed layer salt content

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** February 2012

**Last modified** June 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number

**alias** = ‘mlotstsc’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod** `generate_jobs` (*diags, options*)  
Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – None

**Returns**

### 8.3.13 earthdiagnostics.ocean.moc

**class** `earthdiagnostics.ocean.moc.Moc` (*data\_manager, startdate, member, chunk*)

Bases: `earthdiagnostics.diagnostic.Diagnostic`

Compute the MOC for oceanic basins

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** March 2012

**Last modified** June 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk's number

**alias** = 'moc'

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod** `generate_jobs` (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – None

**Returns**

### 8.3.14 earthdiagnostics.ocean.psi

**class** `earthdiagnostics.ocean.psi.Psi` (*data\_manager, startdate, member, chunk*)

Bases: `earthdiagnostics.diagnostic.Diagnostic`

Compute the barotropic stream function

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor<javier.vegas@bsc.es>

**Created** March 2012

**Last modified** June 2016

**Parameters**

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number

**alias** = ‘psi’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – None

**Returns**

### 8.3.15 earthdiagnostics.ocean.siasiesiv

**class** earthdiagnostics.ocean.siasiesiv.**Siasiesiv** (*data\_manager, startdate, member, chunk, basin, mask*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Compute the sea ice extent , area and volume in both hemispheres or a specified region.

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Neven Fuckar <neven.fuckar@bsc.es>

**Contributor** Ruben Cruz <ruben.cruzgarcia@bsc.es>

**Contributor** Javier Vegas-Regidor <javier.vegas@bsc.es>

**Created** April 2012

**Last modified** June 2016

**alias** = ‘siasiesiv’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

**Parameters**

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – basin

**Returns**

### 8.3.16 earthdiagnostics.ocean.verticalmean

**class** earthdiagnostics.ocean.verticalmean.**VerticalMean** (*data\_manager, startdate, member, chunk, variable, box*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Chooses vertical level in ocean, or vertically averages between 2 or more ocean levels

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Eleftheria Exarchou <eleftheria.exarchou@bsc.es>

**Contributor** Javier Vegas-Regidor <javier.vegas@bsc.es>

**Created** February 2012

**Last modified** June 2016

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk’s number
- **variable** (*str*) – variable to average
- **box** (*Box*) – box used to restrict the vertical mean

**alias** = ‘vertmean’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, minimum depth (level), maximum depth (level)

#### Returns

### 8.3.17 earthdiagnostics.ocean.verticalmeanmeters

**class** earthdiagnostics.ocean.verticalmeanmeters.**VerticalMeanMeters** (*data\_manager, startdate, member, chunk, variable, box*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Averages vertically any given variable

**Original author** Virginie Guemas <virginie.guemas@bsc.es>

**Contributor** Javier Vegas-Regidor <javier.vegas@bsc.es>

**Created** February 2012

Last modified June 2016

#### Parameters

- **data\_manager** (`DataManager`) – data management object
- **startdate** (`str`) – startdate
- **member** (`int`) – member number
- **chunk** (`int`) – chunk’s number
- **variable** (`str`) – variable to average
- **box** (`Box`) – box used to restrict the vertical mean

**alias** = ‘vertmeanmeters’

Diagnostic alias for the configuration file

**compute** ()

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – variable, minimum depth (meters), maximum depth (meters)

#### Returns

## 8.4 earthdiagnostics.statistics

### 8.4.1 earthdiagnostics.statistics.climatologicalpercentile

**class** `earthdiagnostics.statistics.climatologicalpercentile.ClimatologicalPercentile` (*data\_manager, domain, main, variable, lead-times, num\_bins, experiment\_config*)

Bases: `earthdiagnostics.diagnostic.Diagnostic`

Calculates the climatological percentiles for the given leadtimes

#### Parameters

- **data\_manager** (`DataManager`) – data management object
- **variable** (`str`) – variable to average
- **experiment\_config** (`ExperimentConfig`) –

**alias = 'climpercent'**

Diagnostic alias for the configuration file

**compute()**

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – domain, variable, percentil number, maximum depth (level)

#### Returns

## 8.4.2 earthdiagnostics.statistics.monthlypercentile

**class** earthdiagnostics.statistics.monthlypercentile.**MonthlyPercentile** (*data\_manager, startdate, member, chunk, domain, variable, per-centiles*)

Bases: *earthdiagnostics.diagnostic.Diagnostic*

Calculates the montlhy percentiles

#### Parameters

- **data\_manager** (*DataManager*) – data management object
- **startdate** (*str*) – startdate
- **member** (*int*) – member number
- **chunk** (*int*) – chunk's number
- **variable** (*str*) – variable to average

**alias = 'monpercent'**

Diagnostic alias for the configuration file

**compute()**

Runs the diagnostic

**classmethod generate\_jobs** (*diags, options*)

Creates a job for each chunk to compute the diagnostic

#### Parameters

- **diags** (*Diags*) – Diagnostics manager class
- **options** (*list[str]*) – domain, variable, percentil number, maximum depth (level)

#### Returns



**e**

[earthdiagnostics.box](#), 23  
[earthdiagnostics.cdftools](#), 24  
[earthdiagnostics.cmorizer](#), 24  
[earthdiagnostics.cmormanager](#), 24  
[earthdiagnostics.config](#), 27  
[earthdiagnostics.constants](#), 28  
[earthdiagnostics.datamanager](#), 32  
[earthdiagnostics.diagnostic](#), 35  
[earthdiagnostics.earthdiags](#), 36  
[earthdiagnostics.general.attribute](#), 44  
[earthdiagnostics.general.monthlymean](#),  
[44](#)  
[earthdiagnostics.general.relink](#), 45  
[earthdiagnostics.general.relinkall](#), 46  
[earthdiagnostics.general.rewrite](#), 46  
[earthdiagnostics.general.scale](#), 47  
[earthdiagnostics.ocean.areamoc](#), 48  
[earthdiagnostics.ocean.averagesection](#),  
[49](#)  
[earthdiagnostics.ocean.convectionsites](#),  
[49](#)  
[earthdiagnostics.ocean.cutsection](#), 50  
[earthdiagnostics.ocean.gyres](#), 51  
[earthdiagnostics.ocean.heatcontent](#), 52  
[earthdiagnostics.ocean.heatcontentlayer](#),  
[52](#)  
[earthdiagnostics.ocean.interpolate](#), 53  
[earthdiagnostics.ocean.interpolatecdo](#),  
[54](#)  
[earthdiagnostics.ocean.maxmoc](#), 55  
[earthdiagnostics.ocean.mixedlayerheatcontent](#),  
[55](#)  
[earthdiagnostics.ocean.mixedlayersaltcontent](#),  
[56](#)  
[earthdiagnostics.ocean.moc](#), 57  
[earthdiagnostics.ocean.psi](#), 57  
[earthdiagnostics.ocean.siasiesiv](#), 58  
[earthdiagnostics.ocean.verticalmean](#), 59  
[earthdiagnostics.ocean.verticalmeanmeters](#),  
[59](#)  
[earthdiagnostics.parser](#), 37

[earthdiagnostics.statistics.climatologicalpercentile](#),  
[60](#)  
[earthdiagnostics.statistics.monthlypercentile](#),  
[61](#)  
[earthdiagnostics.utils](#), 40  
[earthdiagnostics.variable](#), 43



## A

- `add_conversion()` (earthdiagnostics.datamanager.UnitConversion class method), 35
- `add_section()` (earthdiagnostics.parser.Parser method), 37
- `alias` (earthdiagnostics.diagnostic.Diagnostic attribute), 35
- `alias` (earthdiagnostics.general.attribute.Attribute attribute), 44
- `alias` (earthdiagnostics.general.monthlymean.MonthlyMean attribute), 45
- `alias` (earthdiagnostics.general.relink.Relink attribute), 45
- `alias` (earthdiagnostics.general.relinkall.RelinkAll attribute), 46
- `alias` (earthdiagnostics.general.rewrite.Rewrite attribute), 47
- `alias` (earthdiagnostics.general.scale.Scale attribute), 47
- `alias` (earthdiagnostics.ocean.areamoc.AreaMoc attribute), 48
- `alias` (earthdiagnostics.ocean.averagesection.AverageSection attribute), 49
- `alias` (earthdiagnostics.ocean.convectionsites.ConvectionSites attribute), 50
- `alias` (earthdiagnostics.ocean.cutsection.CutSection attribute), 50
- `alias` (earthdiagnostics.ocean.gyres.Gyres attribute), 51
- `alias` (earthdiagnostics.ocean.heatcontent.HeatContent attribute), 52
- `alias` (earthdiagnostics.ocean.heatcontentlayer.HeatContentLayer attribute), 53
- `alias` (earthdiagnostics.ocean.interpolate.Interpolate attribute), 53
- `alias` (earthdiagnostics.ocean.interpolatecdo.InterpolateCDO attribute), 54
- `alias` (earthdiagnostics.ocean.maxmoc.MaxMoc attribute), 55
- `alias` (earthdiagnostics.ocean.mixedlayerheatcontent.MixedLayerHeatContent attribute), 56
- `alias` (earthdiagnostics.ocean.mixedlayersaltcontent.MixedLayerSaltContent attribute), 56
- `alias` (earthdiagnostics.ocean.moc.Moc attribute), 57
- `alias` (earthdiagnostics.ocean.psi.Psi attribute), 58
- `alias` (earthdiagnostics.ocean.siasiesiv.Siasiesiv attribute), 58
- `alias` (earthdiagnostics.ocean.verticalmean.VerticalMean attribute), 59
- `alias` (earthdiagnostics.ocean.verticalmeanmeters.VerticalMeanMeters attribute), 60
- `alias` (earthdiagnostics.statistics.climatologicalpercentile.ClimatologicalPercentile attribute), 60
- `alias` (earthdiagnostics.statistics.monthlypercentile.MonthlyPercentile attribute), 61
- Antarctic (earthdiagnostics.constants.Basins attribute), 28
- AntarcticAtlantic (earthdiagnostics.constants.Basins attribute), 28
- AntarcticIndian (earthdiagnostics.constants.Basins attribute), 28
- Arctic (earthdiagnostics.constants.Basins attribute), 28
- ArcticMarginalSeas (earthdiagnostics.constants.Basins attribute), 28
- ArcticNorthAtlantic (earthdiagnostics.constants.Basins attribute), 28
- AreaMoc (class in earthdiagnostics.ocean.areamoc), 48
- Atlantic (earthdiagnostics.constants.Basins attribute), 28
- Attribute (class in earthdiagnostics.general.attribute), 44
- autoclean (earthdiagnostics.utils.TempFile attribute), 40
- `available_cpu_count()` (earthdiagnostics.utils.Utils static method), 41
- AverageSection (class in earthdiagnostics.ocean.averagesection), 49

## B

- Baffin (earthdiagnostics.constants.Basins attribute), 29
- Baffin\_Bay (earthdiagnostics.constants.Basins attribute), 29
- Baltic\_Sea (earthdiagnostics.constants.Basins attribute), 29
- Barents\_Sea (earthdiagnostics.constants.Basins attribute), 29
- Gibuti (earthdiagnostics.constants.Basins attribute), 29
- BarKara (earthdiagnostics.constants.Basins attribute), 29
- Basin (class in earthdiagnostics.constants), 28
- Basins (class in earthdiagnostics.constants), 28
- Beaufort\_Chukchi\_Sea (earthdiagnostics.constants.Basins attribute), 29

Beaufort\_Sea (earthdiagnostics.constants.Basins attribute), 29  
 Bellingshausen\_Sea (earthdiagnostics.constants.Basins attribute), 29  
 Bering (earthdiagnostics.constants.Basins attribute), 29  
 Bering\_Strait (earthdiagnostics.constants.Basins attribute), 29  
 Box (class in earthdiagnostics.box), 23  
 box (earthdiagnostics.constants.Basin attribute), 28

## C

Canadian\_Waters (earthdiagnostics.constants.Basins attribute), 29  
 CanArch (earthdiagnostics.constants.Basins attribute), 29  
 Caspian\_Sea (earthdiagnostics.constants.Basins attribute), 29  
 CDFTools (class in earthdiagnostics.cdftools), 24  
 cdftools\_path (earthdiagnostics.config.Config attribute), 27  
 cdo (earthdiagnostics.utils.Utils attribute), 41  
 Central\_Arctic (earthdiagnostics.constants.Basins attribute), 29  
 check\_exists() (earthdiagnostics.parser.Parser method), 37  
 check\_is\_boolean() (earthdiagnostics.parser.Parser method), 37  
 check\_is\_choice() (earthdiagnostics.parser.Parser method), 37  
 check\_is\_int() (earthdiagnostics.parser.Parser method), 37  
 check\_regex() (earthdiagnostics.parser.Parser method), 38  
 Chukchi\_Sea (earthdiagnostics.constants.Basins attribute), 29  
 clean() (earthdiagnostics.utils.TempFile static method), 40  
 ClimatologicalPercentile (class in earthdiagnostics.statistics.climatologicalpercentile), 60  
 cmorize\_atmos() (earthdiagnostics.cmorizer.Cmorizer method), 24  
 cmorize\_ocean() (earthdiagnostics.cmorizer.Cmorizer method), 24  
 Cmorizer (class in earthdiagnostics.cmorizer), 24  
 CMORManager (class in earthdiagnostics.cmormanager), 24  
 compute() (earthdiagnostics.diagnostic.Diagnostic method), 35  
 compute() (earthdiagnostics.general.attribute.Attribute method), 44  
 compute() (earthdiagnostics.general.monthlymean.MonthlyMean method), 45  
 compute() (earthdiagnostics.general.relink.Relink method), 45

compute() (earthdiagnostics.general.relinkall.RelinkAll method), 46  
 compute() (earthdiagnostics.general.rewrite.Rewrite method), 47  
 compute() (earthdiagnostics.general.scale.Scale method), 47  
 compute() (earthdiagnostics.ocean.areamoc.AreaMoc method), 48  
 compute() (earthdiagnostics.ocean.averagesection.AverageSection method), 49  
 compute() (earthdiagnostics.ocean.convectionsites.ConvectionSites method), 50  
 compute() (earthdiagnostics.ocean.cutsection.CutSection method), 51  
 compute() (earthdiagnostics.ocean.gyres.Gyres method), 51  
 compute() (earthdiagnostics.ocean.heatcontent.HeatContent method), 52  
 compute() (earthdiagnostics.ocean.heatcontentlayer.HeatContentLayer method), 53  
 compute() (earthdiagnostics.ocean.interpolate.Interpolate method), 54  
 compute() (earthdiagnostics.ocean.interpolatecdo.InterpolateCDO method), 54  
 compute() (earthdiagnostics.ocean.maxmoc.MaxMoc method), 55  
 compute() (earthdiagnostics.ocean.mixedlayerheatcontent.MixedLayerHeatContent method), 56  
 compute() (earthdiagnostics.ocean.mixedlayersaltcontent.MixedLayerSaltContent method), 56  
 compute() (earthdiagnostics.ocean.moc.Moc method), 57  
 compute() (earthdiagnostics.ocean.psi.Psi method), 58  
 compute() (earthdiagnostics.ocean.siasiesiv.Siasiesiv method), 58  
 compute() (earthdiagnostics.ocean.verticalmean.VerticalMean method), 59  
 compute() (earthdiagnostics.ocean.verticalmeanmeters.VerticalMeanMeters method), 60  
 compute() (earthdiagnostics.statistics.climatologicalpercentile.ClimatologicalPercentile method), 61  
 compute() (earthdiagnostics.statistics.monthlypercentile.MonthlyPercentile method), 61  
 con\_files (earthdiagnostics.config.Config attribute), 27

- concat\_variables() (earthdiagnostics.utils.Utils static method), 41
- Config (class in earthdiagnostics.config), 27
- ConvectionSites (class in earthdiagnostics.ocean.convectionsites), 49
- convert2netcdf4() (earthdiagnostics.utils.Utils static method), 41
- copy\_dimension() (earthdiagnostics.utils.Utils static method), 41
- copy\_file() (earthdiagnostics.utils.Utils static method), 41
- copy\_variable() (earthdiagnostics.utils.Utils static method), 41
- create\_folder\_tree() (earthdiagnostics.utils.Utils static method), 42
- CutSection (class in earthdiagnostics.ocean.cutsection), 50
- ## D
- data\_adaptor (earthdiagnostics.config.Config attribute), 27
- data\_dir (earthdiagnostics.config.Config attribute), 27
- data\_type (earthdiagnostics.config.Config attribute), 27
- DataManager (class in earthdiagnostics.datamanager), 32
- depth\_in\_meters (earthdiagnostics.box.Box attribute), 23
- Diagnostic (class in earthdiagnostics.diagnostic), 35
- ## E
- earthdiagnostics.box (module), 23
- earthdiagnostics.cdfutils (module), 24
- earthdiagnostics.cmorizer (module), 24
- earthdiagnostics.cmormanager (module), 24
- earthdiagnostics.config (module), 27
- earthdiagnostics.constants (module), 28
- earthdiagnostics.datamanager (module), 32
- earthdiagnostics.diagnostic (module), 35
- earthdiagnostics.earthdiags (module), 36
- earthdiagnostics.general.attribute (module), 44
- earthdiagnostics.general.monthlymean (module), 44
- earthdiagnostics.general.relink (module), 45
- earthdiagnostics.general.relinkall (module), 46
- earthdiagnostics.general.rewrite (module), 46
- earthdiagnostics.general.scale (module), 47
- earthdiagnostics.ocean.areamoc (module), 48
- earthdiagnostics.ocean.averagesection (module), 49
- earthdiagnostics.ocean.convectionsites (module), 49
- earthdiagnostics.ocean.cutsection (module), 50
- earthdiagnostics.ocean.gyres (module), 51
- earthdiagnostics.ocean.heatcontent (module), 52
- earthdiagnostics.ocean.heatcontentlayer (module), 52
- earthdiagnostics.ocean.interpolate (module), 53
- earthdiagnostics.ocean.interpolatecdo (module), 54
- earthdiagnostics.ocean.maxmoc (module), 55
- earthdiagnostics.ocean.mixedlayerheatcontent (module), 55
- earthdiagnostics.ocean.mixedlayersaltcontent (module), 56
- earthdiagnostics.ocean.moc (module), 57
- earthdiagnostics.ocean.psi (module), 57
- earthdiagnostics.ocean.siasiesiv (module), 58
- earthdiagnostics.ocean.verticalmean (module), 59
- earthdiagnostics.ocean.verticalmeanmeters (module), 59
- earthdiagnostics.parser (module), 37
- earthdiagnostics.statistics.climatologicalpercentile (module), 60
- earthdiagnostics.statistics.monthlypercentile (module), 61
- earthdiagnostics.utils (module), 40
- earthdiagnostics.variable (module), 43
- EarthDiags (class in earthdiagnostics.earthdiags), 36
- East\_Siberian\_Sea (earthdiagnostics.constants.Basins attribute), 29
- Eastern\_Central\_Arctic (earthdiagnostics.constants.Basins attribute), 29
- ECEARTH\_2\_3\_O1L42 (earthdiagnostics.constants.Models attribute), 32
- ECEARTH\_3\_0\_O1L46 (earthdiagnostics.constants.Models attribute), 32
- ECEARTH\_3\_0\_O25L46 (earthdiagnostics.constants.Models attribute), 32
- ECEARTH\_3\_0\_O25L75 (earthdiagnostics.constants.Models attribute), 32
- ECEARTH\_3\_1\_O25L75 (earthdiagnostics.constants.Models attribute), 32
- ECEARTH\_3\_2\_O1L75 (earthdiagnostics.constants.Models attribute), 32
- execute\_shell\_command() (earthdiagnostics.utils.Utils static method), 42
- expand\_path() (earthdiagnostics.utils.Utils static method), 42
- experiment (earthdiagnostics.config.Config attribute), 27
- ExperimentConfig (class in earthdiagnostics.config), 27
- extract\_variable() (earthdiagnostics.cmorizer.Cmorizer method), 24
- ## F
- file\_exists() (earthdiagnostics.datamanager.DataManager method), 32
- files (earthdiagnostics.utils.TempFile attribute), 40
- Fram\_Strait (earthdiagnostics.constants.Basins attribute), 29
- frequency (earthdiagnostics.config.Config attribute), 27
- fullname (earthdiagnostics.constants.Basin attribute), 28
- ## G
- generate\_jobs() (earthdiagnostics.diagnostic.Diagnostic class method), 35
- generate\_jobs() (earthdiagnostics.general.attribute.Attribute class method),

- [44](#)  
generate\_jobs() (earthdiagnostics.general.monthlymean.MonthlyMean class method), [45](#)
- generate\_jobs() (earthdiagnostics.general.relink.Relink class method), [46](#)
- generate\_jobs() (earthdiagnostics.general.relinkall.RelinkAll class method), [46](#)
- generate\_jobs() (earthdiagnostics.general.rewrite.Rewrite class method), [47](#)
- generate\_jobs() (earthdiagnostics.general.scale.Scale class method), [47](#)
- generate\_jobs() (earthdiagnostics.ocean.areamoc.AreaMoc class method), [48](#)
- generate\_jobs() (earthdiagnostics.ocean.averagesection.AverageSection class method), [49](#)
- generate\_jobs() (earthdiagnostics.ocean.convectionsites.ConvectionSites class method), [50](#)
- generate\_jobs() (earthdiagnostics.ocean.cutsection.CutSection class method), [51](#)
- generate\_jobs() (earthdiagnostics.ocean.gyres.Gyres class method), [51](#)
- generate\_jobs() (earthdiagnostics.ocean.heatcontent.HeatContent class method), [52](#)
- generate\_jobs() (earthdiagnostics.ocean.heatcontentlayer.HeatContentLayer class method), [53](#)
- generate\_jobs() (earthdiagnostics.ocean.interpolate.Interpolate class method), [54](#)
- generate\_jobs() (earthdiagnostics.ocean.interpolatecdo.InterpolateCDO class method), [54](#)
- generate\_jobs() (earthdiagnostics.ocean.maxmoc.MaxMoc class method), [55](#)
- generate\_jobs() (earthdiagnostics.ocean.mixedlayerheatcontent.MixedLayerHeatContent class method), [56](#)
- generate\_jobs() (earthdiagnostics.ocean.mixedlayersaltcontent.MixedLayerSaltContent class method), [56](#)
- generate\_jobs() (earthdiagnostics.ocean.moc.Moc class method), [57](#)
- generate\_jobs() (earthdiagnostics.ocean.psi.Psi class method), [58](#)
- generate\_jobs() (earthdiagnostics.ocean.siasiesiv.Siasiesiv class method), [58](#)
- generate\_jobs() (earthdiagnostics.ocean.verticalmean.VerticalMean class method), [59](#)
- generate\_jobs() (earthdiagnostics.ocean.verticalmeanmeters.VerticalMeanMeters class method), [60](#)
- generate\_jobs() (earthdiagnostics.statistics.climatologicalpercentile.ClimatologicalPercentile class method), [61](#)
- generate\_jobs() (earthdiagnostics.statistics.monthlypercentile.MonthlyPercentile class method), [61](#)
- get() (earthdiagnostics.parser.Parser method), [38](#)
- get() (earthdiagnostics.utils.TempFile static method), [40](#)
- get\_bool\_option() (earthdiagnostics.parser.Parser method), [38](#)
- get\_chunk\_list() (earthdiagnostics.config.ExperimentConfig method), [27](#)
- get\_commands() (earthdiagnostics.config.Config method), [27](#)
- get\_conversion\_factor\_offset() (earthdiagnostics.datamanager.UnitConversion class method), [35](#)
- get\_datetime\_from\_netcdf() (earthdiagnostics.utils.Utils static method), [42](#)
- get\_depth\_str() (earthdiagnostics.box.Box method), [23](#)
- get\_diagnostic() (earthdiagnostics.diagnostic.Diagnostic static method), [36](#)
- get\_file() (earthdiagnostics.cmormanager.CMORManager method), [24](#)
- get\_file() (earthdiagnostics.datamanager.DataManager method), [33](#)
- get\_file\_hash() (earthdiagnostics.utils.Utils static method), [42](#)
- get\_file\_path() (earthdiagnostics.cmormanager.CMORManager method), [25](#)
- get\_float\_option() (earthdiagnostics.parser.Parser method), [38](#)
- get\_full\_years() (earthdiagnostics.config.ExperimentConfig method), [27](#)
- get\_int\_option() (earthdiagnostics.parser.Parser method), [39](#)
- get\_lat\_str() (earthdiagnostics.box.Box method), [23](#)
- get\_list\_option() (earthdiagnostics.parser.Parser method), [39](#)
- get\_lon\_str() (earthdiagnostics.box.Box method), [23](#)
- get\_mask() (earthdiagnostics.utils.Utils static method), [42](#)
- get\_member\_list() (earthdiagnostics.config.ExperimentConfig method), [27](#)
- get\_member\_str() (earthdiagnostics.config.ExperimentConfig method), [28](#)

- [get\\_option\(\)](#) (earthdiagnostics.parser.Parser method), [39](#)  
[get\\_year\(\)](#) (earthdiagnostics.cmormanager.CMORManager method), [25](#)  
[get\\_year\(\)](#) (earthdiagnostics.datamanager.DataManager method), [33](#)  
[get\\_year\\_chunks\(\)](#) (earthdiagnostics.config.ExperimentConfig method), [28](#)  
[Global](#) (earthdiagnostics.constants.Basins attribute), [29](#)  
[Global\\_Ocean](#) (earthdiagnostics.constants.Basins attribute), [29](#)  
[GLORYS2\\_V1\\_O25L75](#) (earthdiagnostics.constants.Models attribute), [32](#)  
[Greenland\\_Sea](#) (earthdiagnostics.constants.Basins attribute), [29](#)  
[Grnland](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[Gyres](#) (class in earthdiagnostics.ocean.gyres), [51](#)
- ## H
- [has\\_option\(\)](#) (earthdiagnostics.parser.Parser method), [39](#)  
[has\\_section\(\)](#) (earthdiagnostics.parser.Parser method), [39](#)  
[HeatContent](#) (class in earthdiagnostics.ocean.heatcontent), [52](#)  
[HeatContentLayer](#) (class in earthdiagnostics.ocean.heatcontentlayer), [52](#)  
[Hudson](#) (earthdiagnostics.constants.Basins attribute), [30](#)
- ## I
- [Icelandic\\_Sea](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[Indian](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[IndoPacific](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[Interpolate](#) (class in earthdiagnostics.ocean.interpolate), [53](#)  
[InterpolateCDO](#) (class in earthdiagnostics.ocean.interpolatecdo), [54](#)  
[Irminger\\_Sea](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[items\(\)](#) (earthdiagnostics.parser.Parser method), [39](#)
- ## K
- [Kara\\_Gate\\_Strait](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[Kara\\_Sea](#) (earthdiagnostics.constants.Basins attribute), [30](#)
- ## L
- [Labrador\\_Sea](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[Laptev\\_East\\_Siberian\\_Chukchi\\_Seas](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[Laptev\\_East\\_Siberian\\_Seas](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[Laptev\\_Sea](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[Lincoln\\_Sea](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[link\\_file\(\)](#) (earthdiagnostics.cmormanager.CMORManager method), [25](#)  
[link\\_file\(\)](#) (earthdiagnostics.datamanager.DataManager method), [33](#)  
[load\\_conversions\(\)](#) (earthdiagnostics.datamanager.UnitConversion class method), [35](#)
- ## M
- [max\\_cores](#) (earthdiagnostics.config.Config attribute), [27](#)  
[max\\_depth](#) (earthdiagnostics.box.Box attribute), [23](#)  
[max\\_lat](#) (earthdiagnostics.box.Box attribute), [23](#)  
[max\\_lon](#) (earthdiagnostics.box.Box attribute), [23](#)  
[MaxMoc](#) (class in earthdiagnostics.ocean.maxmoc), [55](#)  
[Mediterranean\\_Sea](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[min\\_depth](#) (earthdiagnostics.box.Box attribute), [23](#)  
[min\\_lat](#) (earthdiagnostics.box.Box attribute), [23](#)  
[min\\_lon](#) (earthdiagnostics.box.Box attribute), [23](#)  
[MixedLayerHeatContent](#) (class in earthdiagnostics.ocean.mixedlayerheatcontent), [55](#)  
[MixedLayerSaltContent](#) (class in earthdiagnostics.ocean.mixedlayersaltcontent), [56](#)  
[Moc](#) (class in earthdiagnostics.ocean.moc), [57](#)  
[Models](#) (class in earthdiagnostics.constants), [31](#)  
[MonthlyMean](#) (class in earthdiagnostics.general.monthlymean), [44](#)  
[MonthlyPercentile](#) (class in earthdiagnostics.statistics.monthlypercentile), [61](#)  
[move\\_file\(\)](#) (earthdiagnostics.utils.Utils static method), [42](#)
- ## N
- [Nares\\_Strait](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[nco](#) (earthdiagnostics.utils.Utils attribute), [42](#)  
[NEMO\\_3\\_2\\_O1L42](#) (earthdiagnostics.constants.Models attribute), [32](#)  
[NEMO\\_3\\_3\\_O1L46](#) (earthdiagnostics.constants.Models attribute), [32](#)  
[NEMO\\_3\\_6\\_O1L46](#) (earthdiagnostics.constants.Models attribute), [32](#)  
[NEMOVAR\\_O1L42](#) (earthdiagnostics.constants.Models attribute), [32](#)  
[NetCDFFile](#) (class in earthdiagnostics.datamanager), [34](#)  
[Nordic\\_Barents\\_Seas](#) (earthdiagnostics.constants.Basins attribute), [30](#)  
[Nordic\\_Seas](#) (earthdiagnostics.constants.Basins attribute), [30](#)

North\_Atlantic\_Arctic (earthdiagnostics.constants.Basins attribute), 30  
 North\_Hemisphere\_Ocean (earthdiagnostics.constants.Basins attribute), 31  
 NorthAtlantic (earthdiagnostics.constants.Basins attribute), 30  
 NorthPacific (earthdiagnostics.constants.Basins attribute), 30  
 NorthWest\_Passage (earthdiagnostics.constants.Basins attribute), 30  
 Norwegian\_Sea (earthdiagnostics.constants.Basins attribute), 31

## O

Okhotsk (earthdiagnostics.constants.Basins attribute), 31  
 openCdf() (earthdiagnostics.utils.Utils static method), 43  
 OpenOcean (earthdiagnostics.constants.Basins attribute), 31  
 options() (earthdiagnostics.parser.Parser method), 39

## P

Pacific (earthdiagnostics.constants.Basins attribute), 31  
 parse() (earthdiagnostics.constants.Basins class method), 31  
 parse\_args() (earthdiagnostics.earthdiags.EarthDiags static method), 36  
 Parser (class in earthdiagnostics.parser), 37  
 prefix (earthdiagnostics.utils.TempFile attribute), 41  
 prepare() (earthdiagnostics.cmormanager.CMORManager method), 26  
 prepare() (earthdiagnostics.datamanager.DataManager method), 34  
 Psi (class in earthdiagnostics.ocean.psi), 57

## R

read() (earthdiagnostics.parser.Parser method), 40  
 readfp() (earthdiagnostics.parser.Parser method), 40  
 register() (earthdiagnostics.diagnostic.Diagnostic static method), 36  
 Relink (class in earthdiagnostics.general.relink), 45  
 RelinkAll (class in earthdiagnostics.general.relinkall), 46  
 remove\_file() (earthdiagnostics.utils.Utils static method), 43  
 remove\_option() (earthdiagnostics.parser.Parser method), 40  
 remove\_section() (earthdiagnostics.parser.Parser method), 40  
 rename\_variable() (earthdiagnostics.utils.Utils static method), 43  
 rename\_variables() (earthdiagnostics.utils.Utils static method), 43  
 restore\_meshes (earthdiagnostics.config.Config attribute), 27

Rewrite (class in earthdiagnostics.general.rewrite), 46  
 Ross\_Sea (earthdiagnostics.constants.Basins attribute), 31  
 run() (earthdiagnostics.cdftools.CDFTools method), 24  
 run() (earthdiagnostics.earthdiags.EarthDiags method), 37

## S

Scale (class in earthdiagnostics.general.scale), 47  
 scratch\_dir (earthdiagnostics.config.Config attribute), 27  
 scratch\_folder (earthdiagnostics.utils.TempFile attribute), 41  
 sections() (earthdiagnostics.parser.Parser method), 40  
 send\_file() (earthdiagnostics.cmormanager.CMORManager method), 26  
 send\_file() (earthdiagnostics.datamanager.DataManager method), 34  
 send\_file() (earthdiagnostics.diagnostic.Diagnostic method), 36  
 Serreze\_Arctic (earthdiagnostics.constants.Basins attribute), 31  
 set() (earthdiagnostics.parser.Parser method), 40  
 setminmax() (earthdiagnostics.utils.Utils static method), 43  
 shortname (earthdiagnostics.constants.Basin attribute), 28  
 Siasiesiv (class in earthdiagnostics.ocean.siasiesiv), 58  
 Southern\_Hemisphere (earthdiagnostics.constants.Basins attribute), 31  
 StLawr (earthdiagnostics.constants.Basins attribute), 31  
 Subpolar\_Gyre (earthdiagnostics.constants.Basins attribute), 31

## T

TempFile (class in earthdiagnostics.utils), 40  
 TotalArc (earthdiagnostics.constants.Basins attribute), 31  
 TropicalAtlantic (earthdiagnostics.constants.Basins attribute), 31  
 TropicalIndian (earthdiagnostics.constants.Basins attribute), 31  
 TropicalPacific (earthdiagnostics.constants.Basins attribute), 31

## U

UnitConversion (class in earthdiagnostics.datamanager), 35  
 untar() (earthdiagnostics.utils.Utils static method), 43  
 unzip() (earthdiagnostics.utils.Utils static method), 43  
 Utils (class in earthdiagnostics.utils), 41  
 Utils.ExecutionError, 41  
 Utils.UnzipException, 41

## V

Variable (class in earthdiagnostics.variable), 43

VariableAlias (class in earthdiagnostics.variable), [43](#)  
 VerticalMean (class in earthdiagnostics.ocean.verticalmean), [59](#)  
 VerticalMeanMeters (class in earthdiagnostics.ocean.verticalmeanmeters), [59](#)  
 Vilkitsky\_Strait (earthdiagnostics.constants.Basins attribute), [31](#)

## W

Weddell\_Sea (earthdiagnostics.constants.Basins attribute), [31](#)  
 Western\_Central\_Arctic (earthdiagnostics.constants.Basins attribute), [31](#)  
 write() (earthdiagnostics.parser.Parser method), [40](#)